

SAP ABAP table OIU_DO_JV {PRA venture extension}

OIU_DO_JV-ACQ_FROM_KUNNR = KNA1-KUNNR

0..N

KNA1
<u>MANDT</u> [CLNT (3)]
<u>KUNNR</u> [CHAR (10)]

OIU_DO_JV-SLD_TO_KUNNR = KNA1-KUNNR

0..N

OIU_CM_LXPGL
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]
<u>PRI_GEO_LOC</u> [CHAR (2)]

OIU_DO_JV-PRI_GEO_LOC = OIU_CM_LXPGL-PRI_GEO_LOC

0..N

1

1

OIU_DO_JV
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>VNAME</u> [CHAR (6)]
<u>STS_CODE</u> [CHAR (2)]
<u>COUNTRY</u> [CHAR (3)]
<u>PRI_GEO_LOC</u> [CHAR (2)]
<u>SEC_GEO_LOC</u> [CHAR (3)]
<u>ACQ_FROM_KUNNR</u> [CHAR (10)]
<u>SLD_TO_KUNNR</u> [CHAR (10)]
<u>FIELD</u> [CHAR (10)]

OIU_CM_LXSGL
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]
<u>PRI_GEO_LOC</u> [CHAR (2)]
<u>SEC_GEO_LOC</u> [CHAR (3)]

OIU_DO_JV-SEC_GEO_LOC = OIU_CM_LXSGL-SEC_GEO_LOC

0..N

1

OIU_DO_JV-STS_CODE = OIU_CM_VNAMST-VNAME_STATUS

1

1

OIU_CM_VNAMST
<u>MANDT</u> [CLNT (3)]
<u>VNAME_STATUS</u> [CHAR (2)]

OIU_DO_JV-FIELD = OIU_PR_FIELD-FIELD

0..N

0..N

OIU_PR_FIELD
<u>MANDT</u> [CLNT (3)]
<u>FIELD</u> [CHAR (10)]

OIU_DO_JV-BUKRS = T001-BUKRS

0..N

1

1

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

OIU_DO_JV-COUNTRY = T005-LAND1

0..N

T005
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]

0..N