

SAP ABAP table OIUY3_TX_INTSTG {Royalty 2.0 - TX GLO - Royalty Trans Interface Staging}

OIUY3_TX_INTSTG
<u>MANDT</u> [CLNT (3)]
OR_LVL_1_NO [CHAR (3)]
ACCT_PERD_DT [CHAR (8)]
BTCH_NO [CHAR (4)]
LE_NO [CHAR (8)]
BUKRS [CHAR (4)]
PDCD [CHAR (3)]
WL_NO [CHAR (15)]
WC_NO [CHAR (5)]
MP_NO [CHAR (20)]
VNAME [CHAR (6)]
DOI_NO [CHAR (5)]
DN_NO [CHAR (20)]
CT_NO [CHAR (10)]
VL_TYPE_CD [CHAR (2)]
UNIT_VNAME [CHAR (6)]
UOM [UNIT (3)]
GLO_LEASE [NUMC (6)]
GLO_UNIT_NO [CHAR (4)]
OPERATOR_NO [CHAR (6)]

OIUH_CM_BA
<u>MANDT</u> [CLNT (3)]
BA_BA_NO [CHAR (6)]
BA_SEQ_NO [CHAR (2)]

OIUX3_PDCD
<u>PDCD</u> [CHAR (3)]

OIUY3_TX_LEASE
<u>MANDT</u> [CLNT (3)]
GLO_LEASE [NUMC (6)]

OIUY3_TX_UNIT
<u>MANDT</u> [CLNT (3)]
GLO_UNIT_NO [CHAR (4)]
EFF_FROM_DT [DATS (8)]
<u>GLO_LEASE</u> [NUMC (6)]

OIU_CM_COMPC
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

OIU_DO_DI
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>VNAME</u> [CHAR (6)]
<u>DOI_NO</u> [CHAR (5)]

OIU_DO_JV
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]
<u>VNAME</u> [CHAR (6)]

OIU_PR_DN
<u>MANDT</u> [CLNT (3)]
<u>DN_NO</u> [CHAR (20)]

OIU_PR_MP
<u>MANDT</u> [CLNT (3)]
<u>MP_NO</u> [CHAR (20)]

OIU_PR_VLTYP
<u>VL_TYPE_CD</u> [CHAR (2)]

OIU_PR_WC
<u>MANDT</u> [CLNT (3)]
<u>WL_NO</u> [CHAR (15)]
<u>WC_NO</u> [CHAR (5)]

OIU_PR_WELL
<u>MANDT</u> [CLNT (3)]
<u>WL_NO</u> [CHAR (15)]

OIU_RV_CT
<u>MANDT</u> [CLNT (3)]
<u>CT_NO</u> [CHAR (10)]

T000
<u>MANDT</u> [CLNT (3)]

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

