

SAP ABAP table P0785 {HR Master Record for Infotype 0785}

P0785-BEGR_BETRAG_WAER = T500W-WAERS

T500W
<u>MANDT</u> [CLNT (3)]
<u>LAND1</u> [CHAR (3)]
<u>WAERS</u> [CUKY (5)]

P0785-MAN_KAPBETR_WAER = T500W-WAERS

P0785-TRFGR08 = T510-TRFGR

T510
<u>MANDT</u> [CLNT (3)]
<u>MOLGA</u> [CHAR (2)]
<u>TRFAR</u> [CHAR (2)]
<u>TRFGB</u> [CHAR (2)]
<u>TRFKZ</u> [CHAR (1)]
<u>TRFGR</u> [CHAR (8)]
<u>TRFST</u> [CHAR (2)]
<u>LGART</u> [CHAR (4)]
<u>ENDDA</u> [DATS (8)]

P0785-TRFGR90 = T510-TRFGR

P0785-TRFGR_ENDE_EHE = T510-TRFGR

P0785-TRFST08 = T510-TRFST

P0785-TRFST90 = T510-TRFST

P0785-TRFST_ENDE_EHE = T510-TRFST

P0785-TRFAR08 = T510A-TRFAR

P0785-TRFAR90 = T510A-TRFAR

P0785-TRFAR_ENDE_EHE = T510A-TRFAR

P0785-TRFGB = T510G-TRFGB

P0785-TRFGB08 = T510G-TRFGB

P0785-TRFGB90 = T510G-TRFGB

P0785-TRFGB_ENDE_EHE = T510G-TRFGB

P0785-PREAS = T530E-PREAS

P0785-INFTY = T582A-INFTY

T510A
<u>MANDT</u> [CLNT (3)]
<u>MOLGA</u> [CHAR (2)]
<u>TRFAR</u> [CHAR (2)]

T510G
<u>MANDT</u> [CLNT (3)]
<u>MOLGA</u> [CHAR (2)]
<u>TRFGB</u> [CHAR (2)]

T530E
<u>MANDT</u> [CLNT (3)]
<u>INFTY</u> [CHAR (4)]
<u>PREAS</u> [CHAR (2)]

T582A
<u>MANDT</u> [CLNT (3)]
<u>INFTY</u> [CHAR (4)]

P0785
<u>INFTY</u> [CHAR (4)]
<u>PREAS</u> [CHAR (2)]
<u>BEGR_BETRAG_WAER</u> [CUKY (5)]
<u>TRFGB</u> [CHAR (2)]
<u>TRFGR90</u> [CHAR (8)]
<u>TRFST90</u> [CHAR (2)]
<u>TRFAR90</u> [CHAR (2)]
<u>TRFGB90</u> [CHAR (2)]
<u>MAN_KAPBETR_WAER</u> [CUKY (5)]
<u>TRFAR08</u> [CHAR (2)]
<u>TRFGB08</u> [CHAR (2)]
<u>TRFGR08</u> [CHAR (8)]
<u>TRFST08</u> [CHAR (2)]
<u>TRFAR_ENDE_EHE</u> [CHAR (2)]
<u>TRFGB_ENDE_EHE</u> [CHAR (2)]
<u>TRFGR_ENDE_EHE</u> [CHAR (8)]
<u>TRFST_ENDE_EHE</u> [CHAR (2)]