

# SAP ABAP table P5136 {Infotype 5136: Correspondence}

P5136-MANDT = T000-MANDT

0..N

<b>T000</b>
<u>MANDT</u> [CLNT (3)]

P5136-OTYPE = T778O-OTYPE

0..N

<b>T778O</b>
<u>MANDT</u> [CLNT (3)]
<u>OTYPE</u> [CHAR (2)]

P5136-RES\_SCLAS = T778O-OTYPE

0..N

<b>T778P</b>
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]

P5136-PLVAR = T778P-PLVAR

0..N

<b>T778S</b>
<u>MANDT</u> [CLNT (3)]
<u>ISTAT</u> [CHAR (1)]

P5136-ISTAT = T778S-ISTAT

0..N

P5136-INFTY = T778T-INFTY

0..N

<b>T778T</b>
<u>MANDT</u> [CLNT (3)]
<u>INFTY</u> [CHAR (4)]

P5136-SUBTY = T778U-SUBTY

0..N

<b>T778U</b>
<u>MANDT</u> [CLNT (3)]
<u>INFTY</u> [CHAR (4)]
<u>SUBTY</u> [CHAR (4)]

P5136-ACT\_CAT = T77RCF\_ACT\_CAT-ACT\_CAT

0..N

<b>T77RCF_ACT_CAT</b>
<u>MANDT</u> [CLNT (3)]
<u>ACT_CAT</u> [NUMC (2)]

P5136-ACT\_TYPE = T77RCF\_ACT\_TYPE-ACT\_TYPE

0..N

<b>T77RCF_ACT_TYPE</b>
<u>MANDT</u> [CLNT (3)]
<u>ACT_TYPE</u> [CHAR (4)]

0..N

<b>P5136</b>
<u>MANDT</u> [CLNT (3)]
<u>PLVAR</u> [CHAR (2)]
<u>OTYPE</u> [CHAR (2)]
<u>INFTY</u> [CHAR (4)]
<u>SUBTY</u> [CHAR (4)]
<u>ISTAT</u> [CHAR (1)]
<u>ACT_TYPE</u> [CHAR (4)]
<u>RES_SCLAS</u> [CHAR (2)]
<u>ACT_CAT</u> [NUMC (2)]

0..N, 0..N

0..N

0..N

0..N

0..N

0..N

0..N, 0..N