

SAP ABAP table PA0602 {HR Master Record: Infotype 0602 (Retirement Plan Cumulation)}

PA0602
<u>MANDT</u> [CLNT (3)]
<u>PERNR</u> [NUMC (8)]
<u>SUBTY</u> [CHAR (4)]
<u>OBJPS</u> [CHAR (2)]
<u>SPRPS</u> [CHAR (1)]
<u>ENDDA</u> [DATS (8)]
<u>BEGDA</u> [DATS (8)]
<u>SEQNR</u> [NUMC (3)]
<u>PREAS</u> [CHAR (2)]
<u>BAREA</u> [CHAR (2)]
<u>BPLAN</u> [CHAR (4)]
<u>CUMTY</u> [CHAR (1)]
<u>CURRE</u> [CUKY (5)]

PA0602-PERNR = PA0003-PERNR 0..N

PA0003
<u>MANDT</u> [CLNT (3)]
<u>PERNR</u> [NUMC (8)]

PA0602-PREAS = T530E-PREAS 0..N

T530E
<u>MANDT</u> [CLNT (3)]
<u>INFTY</u> [CHAR (4)]
<u>PREAS</u> [CHAR (2)]

PA0602-CUMTY = T54C2-CUMTY 0..N

T54C2
<u>MANDT</u> [CLNT (3)]
<u>CUMTY</u> [CHAR (1)]

{0,1} PA0602-BAREA = T5UB3-BAREA

T5UB3
<u>MANDT</u> [CLNT (3)]
<u>BAREA</u> [CHAR (2)]

1 PA0602-BPLAN = T5UBA-BPLAN 0..N

T5UBA
<u>MANDT</u> [CLNT (3)]
<u>BAREA</u> [CHAR (2)]
<u>BPLAN</u> [CHAR (4)]
<u>ENDDA</u> [DATS (8)]

{0,1} PA0602-CURRE = TCURC-WAERS 0..N

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]