

SAP ABAP table PA0804 {Personnel Master Record Infotype 0804}

PA0804
<u>MANDT</u> [CLNT (3)]
<u>PERNR</u> [NUMC (8)]
<u>SUBTY</u> [CHAR (4)]
<u>OBJPS</u> [CHAR (2)]
<u>SPRPS</u> [CHAR (1)]
<u>ENDDA</u> [DATS (8)]
<u>BEGDA</u> [DATS (8)]
<u>SEQNR</u> [NUMC (3)]
<u>PREAS</u> [CHAR (2)]
<u>HUNIT</u> [UNIT (3)]
<u>WUNIT</u> [UNIT (3)]
<u>ECOLR</u> [CHAR (4)]
<u>HCOLR</u> [CHAR (4)]

_ISDFPS_VCOLOREY
<u>MANDT</u> [CLNT (3)]
<u>MOLGA</u> [CHAR (2)]
<u>COLCD</u> [CHAR (4)]

_ISDFPS_VCOLORHA
<u>MANDT</u> [CLNT (3)]
<u>MOLGA</u> [CHAR (2)]
<u>COLCD</u> [CHAR (4)]

_ISDFPS_VT006LEN
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

_ISDFPS_VT006MAS
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

PA0003
<u>MANDT</u> [CLNT (3)]
<u>PERNR</u> [NUMC (8)]

T530E
<u>MANDT</u> [CLNT (3)]
<u>INFTY</u> [CHAR (4)]
<u>PREAS</u> [CHAR (2)]

PA0804-ECOLR = /ISDFPS/VCOLOREY-COLCD 0..N

PA0804-HCOLR = /ISDFPS/VCOLORHA-COLCD 0..N

PA0804-HUNIT = /ISDFPS/VT006LEN-MSEHI 0..N

PA0804-WUNIT = /ISDFPS/VT006MAS-MSEHI

PA0804-PERNR = PA0003-PERNR 0..N

PA0804-PREAS = T530E-PREAS 0..N

1

1

1

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N