

SAP ABAP table PIQEDRUN_TR_HEADER {ED Run Header with Related Transcript}

PIQEDRUN_TR_HEADER-TOTEXTCREDTYPE = T7PIQCP-CPUNIT

0..N

T7PIQCP
<u>MANDT</u> [CLNT (3)]
<u>CPUNIT</u> [UNIT (3)]

PIQEDRUN_TR_HEADER-TOTINTCREDTYPE = T7PIQCP-CPUNIT

0..N

PIQEDRUN_TR_HEADER-TRSTATUS = T7PIQREPSTAT-REPSTATE

0..N

T7PIQREPSTAT
<u>MANDT</u> [CLNT (3)]
<u>REPSTATE</u> [CHAR (4)]

PIQEDRUN_TR_HEADER-TOTCALCGPASCALE = T7PIQSCALE-SCALEID

PIQEDRUN_TR_HEADER-TOTEXTGPA1SCALE = T7PIQSCALE-SCALEID

0..N

PIQEDRUN_TR_HEADER-TOTEXTGPA2SCALE = T7PIQSCALE-SCALEID

0..N

PIQEDRUN_TR_HEADER-TOTEXTGPA3SCALE = T7PIQSCALE-SCALEID

0..N

0..N

PIQEDRUN_TR_HEADER-TOTSELFGPASCALE = T7PIQSCALE-SCALEID

0..N

T7PIQSCALE
<u>MANDT</u> [CLNT (3)]
<u>SCALEID</u> [CHAR (4)]

PIQEDRUN_TR_HEADER-RETURNINDIC = T7PIQTRRETINDIC-RETURNINDIC

0..N

T7PIQTRRETINDIC
<u>MANDT</u> [CLNT (3)]
<u>RETURNINDIC</u> [CHAR (4)]

PIQEDRUN_TR_HEADER-TRANSTYPE = T7PIQTRTRANSTYP-TRANSTYPE

0..N

T7PIQTRTRANSTYP
<u>MANDT</u> [CLNT (3)]
<u>TRANSTYPE</u> [CHAR (4)]

PIQEDRUN_TR_HEADER
TRANSTYPE [CHAR (4)]
TRSTATUS [CHAR (4)]
RETURNINDIC [CHAR (4)]
TOTSELFGPASCALE [CHAR (4)]
TOTEXTGPA1SCALE [CHAR (4)]
TOTEXTGPA2SCALE [CHAR (4)]
TOTEXTGPA3SCALE [CHAR (4)]
TOTCALCGPASCALE [CHAR (4)]
TOTEXTCREDTYPE [UNIT (3)]
TOTINTCREDTYPE [UNIT (3)]