

SAP ABAP table PLM_QM_NOTIF_FIELDS_CUSTOMER {Mobile Quality Notification: Fields for Customer Reference}

PLM_QM_NOTIF_FIELDS_CUSTOMER
SPART [CHAR (2)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]
KUNUM [CHAR (10)]
LS_KDAUF [CHAR (10)]
LS_VBELN [CHAR (10)]

KNA1
<u>MANDT</u> [CLNT (3)]
<u>KUNNR</u> [CHAR (10)]

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

TVBUR
<u>MANDT</u> [CLNT (3)]
<u>VKBUR</u> [CHAR (4)]

TVKGR
<u>MANDT</u> [CLNT (3)]
<u>VKGRP</u> [CHAR (3)]

TVKO
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]

TVTW
<u>MANDT</u> [CLNT (3)]
<u>VTWEG</u> [CHAR (2)]

VBUK
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

PLM_QM_NOTIF_FIELDS_CUSTOMER-KUNUM = KNA1-KUNNR 0..N

PLM_QM_NOTIF_FIELDS_CUSTOMER-SPART = TSPA-SPART 0..N

PLM_QM_NOTIF_FIELDS_CUSTOMER-VKBUR = TVBUR-VKBUR 0..N

PLM_QM_NOTIF_FIELDS_CUSTOMER-VKGRP = TVKGR-VKGRP 0..N

PLM_QM_NOTIF_FIELDS_CUSTOMER-VKORG = TVKO-VKORG 0..N

PLM_QM_NOTIF_FIELDS_CUSTOMER-VTWEG = TVTW-VTWEG 0..N

PLM_QM_NOTIF_FIELDS_CUSTOMER-LS_KDAUF = VBUK-VBELN 0..N

PLM_QM_NOTIF_FIELDS_CUSTOMER-LS_VBELN = VBUK-VBELN 0..N