

SAP ABAP table REBD_BUILDING {Building (VIBDBU)}

REBD_BUILDING-BUKRS = T001-BUKRS

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

TD09
<u>MANDT</u> [CLNT (3)]
<u>SOBJERBBAU</u> [CHAR (1)]

TIV36
<u>MANDT</u> [CLNT (3)]
<u>SUNART</u> [CHAR (8)]

TIV5A
<u>MANDT</u> [CLNT (3)]
<u>SOBJART</u> [NUMC (2)]

TIV83
<u>MANDT</u> [CLNT (3)]
<u>RZUSTAND</u> [NUMC (2)]

TIVAJRLRALOC
<u>MANDT</u> [CLNT (3)]
<u>RLRA</u> [CHAR (6)]
<u>RLRALOC</u> [CHAR (6)]

TIVBDUSGFUNC
<u>MANDT</u> [CLNT (3)]
<u>USGOBJTYP</u> [CHAR (2)]
<u>USGFUNCTION</u> [CHAR (4)]

TIVG1
<u>MANDT</u> [CLNT (3)]
<u>GEMEINDE</u> [CHAR (8)]

TIVXCCHCOND
<u>MANDT</u> [CLNT (3)]
<u>BCOND</u> [NUMC (4)]

TIVXCCHGENSRC
<u>MANDT</u> [CLNT (3)]
<u>ENERGYSRC</u> [NUMC (4)]

TIVXCCHHEAT
<u>MANDT</u> [CLNT (3)]
<u>HEATINGTYPE</u> [NUMC (4)]

TIVXCCHKAT
<u>MANDT</u> [CLNT (3)]
<u>BCATEGORY</u> [NUMC (4)]

TIVXCPTRA CONS
<u>MANDT</u> [CLNT (3)]
<u>CONSLEVEL</u> [CHAR (4)]

USR02
<u>MANDT</u> [CLNT (3)]
<u>BNAME</u> [CHAR (12)]

REBD_BUILDING
BUKRS [CHAR (4)]
SWENR [CHAR (8)]
OBJNR [CHAR (22)]
RESPONSIBLE [CHAR (12)]
USEREXCLUSIVE [CHAR (12)]
RGEBART [NUMC (2)]
JERBBAU [CHAR (1)]
RGEBZUST [NUMC (2)]
SUNUTZA [CHAR (8)]
RLRALOC [CHAR (6)]
GEMEINDE [CHAR (8)]
REINS [UNIT (3)]
WAERS [CUKY (5)]
USGFUNCTION [CHAR (4)]
OBJCOND [NUMC (4)]
OBJCAT [NUMC (4)]
HEATINGTYPE [NUMC (4)]
ENERGYHEAT [NUMC (4)]
ENERGYWATER [NUMC (4)]
CURRENCY [CUKY (5)]
CONDK [CHAR (4)]

