

SAP ABAP table REBD_EQUIPMENT {Equipment (EQUI)}

REBD_EQUIPMENT
MANDT [CLNT (3)]
EQASP [LANG (1)]
BEGRU [CHAR (4)]
EQTYP [CHAR (1)]
EQART [CHAR (10)]
GEWEI [UNIT (3)]
WAERS [CUKY (5)]
ELIEF [CHAR (10)]
HERLD [CHAR (3)]
EQSNR [CHAR (18)]
KMATN [CHAR (18)]
MATNR [CHAR (18)]
WERK [CHAR (4)]
LAGER [CHAR (4)]
CHARGE [CHAR (10)]
KUNDE [CHAR (10)]
WARPL [CHAR (12)]
IMRC_POINT [CHAR (12)]
MGANR [CHAR (20)]
SPARTE [CHAR (2)]
IUID_TYPE [CHAR (10)]
EQUI_SRTYPE [CHAR (10)]
EQUI_SNTYPE [CHAR (2)]

REBD_EQUIPMENT-MGANR = BGMK-MGANR

BGMK
MANDT [CLNT (3)]
MGANR [CHAR (20)]

REBD_EQUIPMENT-EQUI_SRTYPE = COCF_CU_SRTYPE-SRTYPE

COCF_CU_SRTYPE
MANDT [CLNT (3)]
SRTYPE [CHAR (10)]

REBD_EQUIPMENT-EQSNR = EQSE-EQSNR

EQSE
MANDT [CLNT (3)]
EQSNR [CHAR (18)]

REBD_EQUIPMENT-IMRC_POINT = IMPTT-POINT

IMPTT
MANDT [CLNT (3)]
POINT [CHAR (12)]

REBD_EQUIPMENT-KUNDE = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

REBD_EQUIPMENT-ELIEF = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

REBD_EQUIPMENT-KMATN = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

REBD_EQUIPMENT-MATNR = MARA-MATNR

MCH1
MANDT [CLNT (3)]
MATNR [CHAR (18)]
CHARG [CHAR (10)]

REBD_EQUIPMENT-CHARGE = MCH1-CHARG

REBD_EQUIPMENT-WARPL = MPLA-WARPL

MPLA
MANDT [CLNT (3)]
WARPL [CHAR (12)]

REBD_EQUIPMENT-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

REBD_EQUIPMENT-LAGER = T001L-LGORT

T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

REBD_EQUIPMENT-WERK = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

REBD_EQUIPMENT-EQASP = T002-SPRAS

T002
SPRAS [LANG (1)]

REBD_EQUIPMENT-HERLD = T005-LAND1

T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]

REBD_EQUIPMENT-GEWEI = T006-MSEHI

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

REBD_EQUIPMENT-BEGRU = T370B-BEGRU

T370B
MANDT [CLNT (3)]
BEGRU [CHAR (4)]

REBD_EQUIPMENT-EQART = T370K-EQART

T370K
MANDT [CLNT (3)]
EQART [CHAR (10)]

REBD_EQUIPMENT-EQTYP = T370T-EQTYP

T370T
MANDT [CLNT (3)]
EQTYP [CHAR (1)]

REBD_EQUIPMENT-WAERS = TCURC-WAERS

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

REBD_EQUIPMENT-IUID_TYPE = TIUID_TYPE-IUID_TYPE

TIUID_TYPE
IUID_TYPE [CHAR (10)]

REBD_EQUIPMENT-EQUI_SNTYPE = TQ80-QMART

TQ80
MANDT [CLNT (3)]
QMART [CHAR (2)]

REBD_EQUIPMENT-SPARTE = TSPA-SPART

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]