

SAP ABAP table RJHR0300 {IS-M: Screen Fields for Settlement Item Detail Screen}

RJHR0300-INSERTENT = JGTGPNR-GPNR

0..N

JGTGPNR
<u>MANDT</u> [CLNT (3)]
<u>GPNR</u> [CHAR (10)]

RJHR0300-REGULIERER = JGTGPNR-GPNR

0..N

RJHR0300-GRUPPABRNR = JHAGA-GRUPPABRNR

0..N

JHAGA
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_NR</u> [NUMC (3)]
<u>GRUPPABRNR</u> [NUMC (3)]

RJHR0300-AVM_NR = JHAK-AVM_NR

0..N

JHAK
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]

RJHR0300-POS_NR = JHAP-POS_NR

0..N

JHAP
<u>MANDT</u> [CLNT (3)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_NR</u> [NUMC (3)]

RJHR0300-VTNR = JHTMXK-VTNR

0..N

JHTMXK
<u>MANDT</u> [CLNT (3)]
<u>VTNR</u> [CHAR (10)]

RJHR0300-ABRGNR = JHTVAABK-ABRGNR

0..N

JHTVAABK
<u>MANDT</u> [CLNT (3)]
<u>VTNR</u> [NUMC (6)]
<u>ABRGNR</u> [NUMC (4)]

RJHR0300-APOSNR = JHTVAABP-APOSNR

0..N

JHTVAABP
<u>MANDT</u> [CLNT (3)]
<u>VTNR</u> [NUMC (6)]
<u>ABRGNR</u> [NUMC (4)]
<u>APOSNR</u> [NUMC (4)]

RJHR0300-VTNR_BETE = JHTVKO-VTNR

0..N

JHTVKO
<u>MANDT</u> [CLNT (3)]
<u>VTNR</u> [NUMC (6)]

RJHR0300-AB_WEINH = TCURC-WAERS

0..N

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

RJHR0300-SPART = TSPA-SPART

0..N

TSPA
<u>MANDT</u> [CLNT (3)]
<u>SPART</u> [CHAR (2)]

RJHR0300-VKORG = TVKO-VKORG

0..N

TVKO
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]

RJHR0300-VTWEG = TVTW-VTWEG

0..N

TVTW
<u>MANDT</u> [CLNT (3)]
<u>VTWEG</u> [CHAR (2)]

RJHR0300
<u>REGULIERER</u> [CHAR (10)]
<u>INSERTENT</u> [CHAR (10)]
<u>VKORG</u> [CHAR (4)]
<u>VTWEG</u> [CHAR (2)]
<u>SPART</u> [CHAR (2)]
<u>VTNR</u> [CHAR (10)]
<u>VTNR_BETE</u> [NUMC (6)]
<u>ABRGNR</u> [NUMC (4)]
<u>APOSNR</u> [NUMC (4)]
<u>AVM_NR</u> [CHAR (10)]
<u>POS_NR</u> [NUMC (3)]
<u>GRUPPABRNR</u> [NUMC (3)]
<u>AB_WEINH</u> [CUKY (5)]

1,1,1

1

1

{0,1}

1

1

1

1,1,1

1

1

1

1