

SAP ABAP table RJKSDTRANSFER {IS-M: BP Goods Transfer}

RJKSDTRANSFER-TRANSFER FROM = KNA1-KUNNR

0..N

KNA1
<u>MANDT</u> [CLNT (3)]
<u>KUNNR</u> [CHAR (10)]

RJKSDTRANSFER-TRANSFER_TO = KNA1-KUNNR

0..N

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

RJKSDTRANSFER-UNIT = T006-MSEHI

0..N

TVBVK
<u>MANDT</u> [CLNT (3)]
<u>VKBUR</u> [CHAR (4)]
<u>VKGRP</u> [CHAR (3)]

RJKSDTRANSFER-VKGRP = TVBVK-VKGRP

0..N

RJKSDTRANSFER-VKBUR = TVKBZ-VKBUR

TVKBZ
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]
<u>VTWEG</u> [CHAR (2)]
<u>SPART</u> [CHAR (2)]
<u>VKBUR</u> [CHAR (4)]

RJKSDTRANSFER-VKORG = TVKO-VKORG

0..N

TVKO
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]

RJKSDTRANSFER-VTWEG = TVKOV-VTWEG

0..N

TVKOV
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]
<u>VTWEG</u> [CHAR (2)]

RJKSDTRANSFER-SPART = TVTA-SPART

0..N

TVTA
<u>MANDT</u> [CLNT (3)]
<u>VKORG</u> [CHAR (4)]
<u>VTWEG</u> [CHAR (2)]
<u>SPART</u> [CHAR (2)]

RJKSDTRANSFER
<u>VKORG</u> [CHAR (4)]
<u>VTWEG</u> [CHAR (2)]
<u>SPART</u> [CHAR (2)]
<u>VKGRP</u> [CHAR (3)]
<u>VKBUR</u> [CHAR (4)]
<u>TRANSFER_FROM</u> [CHAR (10)]
<u>TRANSFER_TO</u> [CHAR (10)]
<u>UNIT</u> [UNIT (3)]

1

1

0..N

{0,1}

{0,1}

1

1

1

0..N