

SAP ABAP table RPLM_TS_POWL_FUNC_LOC_INFO {Functional Location Powl}

RPLM_TS_POWL_FUNC_LOC_INFO
SPRAS [LANG (1)]
FLTYP [CHAR (1)]
IWERK [CHAR (4)]
SWERK [CHAR (4)]
STORT [CHAR (10)]
BEBER [CHAR (3)]
ABCKZ [CHAR (1)]
BUKRS [CHAR (4)]
ANLNR [CHAR (12)]
ANLUN [CHAR (4)]
GSBER [CHAR (4)]
KOSTL [CHAR (10)]
DAUFN [CHAR (12)]
AUFNR [CHAR (12)]
TRPNR [CHAR (30)]
TPLKZ [CHAR (5)]
SUBMT [CHAR (18)]
BEGRU [CHAR (4)]
RBNR [CHAR (9)]
INGRP [CHAR (3)]
KOKRS [CHAR (4)]
ILOAN [CHAR (12)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
MANDT [CLNT (3)]
OBJNR [CHAR (22)]
ALKEY [CHAR (1)]

RPLM_TS_POWL_FUNC_LOC_INFO-ANLUN = ANLA-ANLN2

ANLA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]

RPLM_TS_POWL_FUNC_LOC_INFO-ANLNR = ANLH-ANLN1

ANLH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

RPLM_TS_POWL_FUNC_LOC_INFO-AUFNR = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

RPLM_TS_POWL_FUNC_LOC_INFO-DAUFN = AUFK-AUFNR

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

RPLM_TS_POWL_FUNC_LOC_INFO-KOSTL = CSKS-KOSTL

IFLOAT
MANDT [CLNT (3)]
ALKEY [CHAR (1)]

RPLM_TS_POWL_FUNC_LOC_INFO-ALKEY = IFLOAT-ALKEY

RPLM_TS_POWL_FUNC_LOC_INFO-ILOAN = ILOA-ILOAN

ILOA
MANDT [CLNT (3)]
ILOAN [CHAR (12)]

RPLM_TS_POWL_FUNC_LOC_INFO-TRPNR = IRLOT-TRPNR

IRLOT
MANDT [CLNT (3)]
TRPNR [CHAR (30)]

RPLM_TS_POWL_FUNC_LOC_INFO-SUBMT = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

RPLM_TS_POWL_FUNC_LOC_INFO-OBJNR = ONR00-OBJNR

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

RPLM_TS_POWL_FUNC_LOC_INFO-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

RPLM_TS_POWL_FUNC_LOC_INFO-BUKRS = T001-BUKRS

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

RPLM_TS_POWL_FUNC_LOC_INFO-IWERK = T001W-WERKS

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

RPLM_TS_POWL_FUNC_LOC_INFO-SWERK = T001W-WERKS

RPLM_TS_POWL_FUNC_LOC_INFO-SPRAS = T002-SPRAS

T002
SPRAS [LANG (1)]

RPLM_TS_POWL_FUNC_LOC_INFO-INGRP = T024I-INGRP

T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

RPLM_TS_POWL_FUNC_LOC_INFO-RBNR = T352B-RBNR

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

RPLM_TS_POWL_FUNC_LOC_INFO-BEBER = T357-BEBER

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

RPLM_TS_POWL_FUNC_LOC_INFO-BEGRU = T370B-BEGRU

T370B
MANDT [CLNT (3)]
BEGRU [CHAR (4)]

RPLM_TS_POWL_FUNC_LOC_INFO-ABCKZ = T370C-ABCKZ

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

RPLM_TS_POWL_FUNC_LOC_INFO-FLTYP = T370F-FLTYP

T370F
MANDT [CLNT (3)]
FLTYP [CHAR (1)]

RPLM_TS_POWL_FUNC_LOC_INFO-TPLKZ = T370S-TPLKZ

T370S
MANDT [CLNT (3)]
TPLKZ [CHAR (5)]

RPLM_TS_POWL_FUNC_LOC_INFO-STORT = T499S-STAND

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

RPLM_TS_POWL_FUNC_LOC_INFO-GSBER = TGSB-GSBER

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

RPLM_TS_POWL_FUNC_LOC_INFO-KOKRS = TKA01-KOKRS

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

RPLM_TS_POWL_FUNC_LOC_INFO-SPART = TSPA-SPART

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

RPLM_TS_POWL_FUNC_LOC_INFO-VKORG = TVKO-VKORG

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

RPLM_TS_POWL_FUNC_LOC_INFO-VTWEG = TVTW-VTWEG

TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]