

# SAP ABAP table S028 {Reporting Point Statistics}

| <b>S028</b>              |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>SSOUR</u> [CHAR (4)]  |
| <u>VRSIO</u> [CHAR (3)]  |
| <u>SPMON</u> [NUMC (6)]  |
| <u>SPTAG</u> [DATS (8)]  |
| <u>SPWOC</u> [NUMC (6)]  |
| <u>SPBUP</u> [NUMC (6)]  |
| <u>WERKS</u> [CHAR (4)]  |
| <u>DISPO</u> [CHAR (3)]  |
| <u>MATNR</u> [CHAR (18)] |
| <u>VERID</u> [CHAR (4)]  |
| <u>MDV01</u> [CHAR (8)]  |
| <u>MDV02</u> [CHAR (8)]  |
| <u>SAFNR</u> [CHAR (12)] |
| <u>VORNR</u> [CHAR (4)]  |
| <u>PERIV</u> [CHAR (2)]  |

| <b>MARA</b>              |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>MATNR</u> [CHAR (18)] |

| <b>MKAL</b>              |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>MATNR</u> [CHAR (18)] |
| <u>WERKS</u> [CHAR (4)]  |
| <u>VERID</u> [CHAR (4)]  |

| <b>SAFK</b>              |
|--------------------------|
| <u>MANDT</u> [CLNT (3)]  |
| <u>AUFNR</u> [CHAR (12)] |

| <b>T000</b>             |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |

| <b>T001W</b>            |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>WERKS</u> [CHAR (4)] |

| <b>T009</b>             |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>PERIV</u> [CHAR (2)] |

| <b>T024D</b>            |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |
| <u>WERKS</u> [CHAR (4)] |
| <u>DISPO</u> [CHAR (3)] |

| <b>T437P</b>              |
|---------------------------|
| <u>MANDT</u> [CLNT (3)]   |
| <u>WERKS</u> [CHAR (4)]   |
| <u>PLAN_ID</u> [CHAR (8)] |

S028-MATNR = MARA-MATNR 0..N

S028-VERID = MKAL-VERID 0..N

S028-SAFNR = SAFK-AUFNR 0..N

S028-MANDT = T000-MANDT 0..N

S028-WERKS = T001W-WERKS 0..N

S028-PERIV = T009-PERIV 0..N

S028-DISPO = T024D-DISPO 0..N

S028-MDV01 = T437P-PLAN\_ID 0..N

S028-MDV02 = T437P-PLAN\_ID 0..N