

SAP ABAP table SDPARTNER_ENHANCED_KUPAV {Extended KUPAV Structure for Selecting Partners}

SDPARTNER_ENHANCED_KUPAV
MANDT [CLNT (3)]
KUNNR [CHAR (10)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
PARVW [CHAR (2)]
KUNN2 [CHAR (10)]
LIFNR [CHAR (10)]
LAND1 [CHAR (3)]
LZONE [CHAR (10)]
REGIO [CHAR (3)]
SPRAS [LANG (1)]
KTOKD [CHAR (4)]
AUFSD [CHAR (2)]
LIFSD [CHAR (2)]
FAKSD [CHAR (2)]

SDPARTNER_ENHANCED_KUPAV-KUNN2 = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

SDPARTNER_ENHANCED_KUPAV-KUNNR = KNA1-KUNNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

SDPARTNER_ENHANCED_KUPAV-LIFNR = LFA1-LIFNR

SDPARTNER_ENHANCED_KUPAV-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

SDPARTNER_ENHANCED_KUPAV-SPRAS = T002-SPRAS

T002
SPRAS [LANG (1)]

SDPARTNER_ENHANCED_KUPAV-LAND1 = T005-LAND1

T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]

SDPARTNER_ENHANCED_KUPAV-REGIO = T005S-BLAND

T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]

SDPARTNER_ENHANCED_KUPAV-KTOKD = T077D-KTOKD

T077D
MANDT [CLNT (3)]
KTOKD [CHAR (4)]

SDPARTNER_ENHANCED_KUPAV-PARVW = TPAR-PARVW

TPAR
MANDT [CLNT (3)]
PARVW [CHAR (2)]

SDPARTNER_ENHANCED_KUPAV-SPART = TSPA-SPART

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

SDPARTNER_ENHANCED_KUPAV-AUFSD = TVAST-AUFSP

TVAST
MANDT [CLNT (3)]
SPRAS [LANG (1)]
AUFSP [CHAR (2)]

SDPARTNER_ENHANCED_KUPAV-FAKSD = TVFS-FAKSP

TVFS
MANDT [CLNT (3)]
FAKSP [CHAR (2)]

SDPARTNER_ENHANCED_KUPAV-VKORG = TVKO-VKORG

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]

SDPARTNER_ENHANCED_KUPAV-LIFSD = TVLS-LIFSP

TVLS
MANDT [CLNT (3)]
LIFSP [CHAR (2)]

SDPARTNER_ENHANCED_KUPAV-VTWEG = TVTW-VTWEG

TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

SDPARTNER_ENHANCED_KUPAV-LZONE = TZONE-ZONE1

TZONE
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
ZONE1 [CHAR (10)]