

SAP ABAP table TE515 {Settlement: Settlement Step (Obsolete)}

TE515-ABWVERVAR = TE515K-VERVAR

TE515-VSNUMR = TE515-VSNUM
TE515-ABWVSNUM = TE515-VSNUM

TE515
<u>MANDT</u> [CLNT (3)]
<u>VERVAR</u> [CHAR (3)]
<u>VSNUM</u> [NUMC (2)]
ZNAM1 [CHAR (3)]
ZNAM2 [CHAR (3)]
ZNAM3 [CHAR (3)]
ZNAM4 [CHAR (3)]
ZNAM5 [CHAR (3)]
SNAM1 [CHAR (3)]
SNAM2 [CHAR (3)]
SNAM3 [CHAR (3)]
SNAM4 [CHAR (3)]
SNAM5 [CHAR (3)]
BTRGRU [CHAR (3)]
ABWVERVAR [CHAR (3)]
ABWVSNUM [NUMC (2)]
FUNCC [CHAR (30)]
VERVARR [CHAR (3)]
VSNUMR [NUMC (2)]

TE515K
<u>MANDT</u> [CLNT (3)]
<u>VERVAR</u> [CHAR (3)]

TE516
<u>MANDT</u> [CLNT (3)]
<u>FNAM</u> [CHAR (3)]

TE519K
<u>MANDT</u> [CLNT (3)]
<u>BTRGRU</u> [CHAR (3)]
<u>WAERS</u> [CUKY (5)]

TFDIR
<u>FUNCNAME</u> [CHAR (30)]

TE515-VERVAR = TE515K-VERVAR 1..N

TE515-VERVARR = TE515K-VERVAR 0..N

TE515-SNAM1 = TE516-FNAM 1..N

TE515-SNAM2 = TE516-FNAM 1..N

TE515-SNAM3 = TE516-FNAM 1..N

TE515-SNAM4 = TE516-FNAM 1..N

TE515-SNAM5 = TE516-FNAM 1..N

TE515-ZNAM1 = TE516-FNAM 1..N

TE515-ZNAM2 = TE516-FNAM 1..N

TE515-ZNAM3 = TE516-FNAM 1..N

TE515-ZNAM4 = TE516-FNAM 1..N

TE515-ZNAM5 = TE516-FNAM 1..N

TE515-BTRGRU = TE519K-BTRGRU 1..N

TE515-FUNCC = TFDIR-FUNCNAME 0..N