

SAP ABAP table TISSR_OUT_FICUS2 {ISSR: var. Platzierung der Felder auf SF mit Hilfe Methoden}

TISSR_OUT_FICUS2-MANDT = T000-MANDT

TISSR_OUT_FICUS2
<i>MANDT</i> [CLNT (3)]
<i>COUNTRY_VAR</i> [CHAR (4)]
<i>LISTTYP</i> [CHAR (10)]
<i>SPALTE</i> [NUMC (3)]
<i>ZEILE</i> [NUMC (3)]
<i>IPOSITION</i> [NUMC (2)]
<i>ACTIV</i> [CHAR (1)]
<i>FIELDNAME</i> [CHAR (70)]
<i>CLSNAME</i> [CHAR (30)]
<i>CMPNAME</i> [CHAR (30)]
<i>EVENT</i> [CHAR (2)]

T000
<i>MANDT</i> [CLNT (3)]

0..N

0..N

0..N

0..N

0..N

0..N

0..N

TISSR_MARECO
<i>MANDT</i> [CLNT (3)]
<i>COUNTRY_VAR</i> [CHAR (4)]

TISSR_OUT_CL
<i>MANDT</i> [CLNT (3)]
<i>CLSNAME</i> [CHAR (30)]

TISSR_OUT_EVT
<i>EVENT</i> [CHAR (2)]

TISSR_OUT_FN
<i>MANDT</i> [CLNT (3)]
<i>FIELDNAME</i> [CHAR (70)]

TISSR_OUT_FNMT
<i>MANDT</i> [CLNT (3)]
<i>FIELDNAME</i> [CHAR (70)]
<i>CLTYP</i> [CHAR (1)]
<i>CMPNAME</i> [CHAR (30)]

TISSR_OUT_LT
<i>MANDT</i> [CLNT (3)]
<i>COUNTRY_VAR</i> [CHAR (4)]
<i>LISTTYP</i> [CHAR (10)]

0..N

0..N

1

1

0..N

1

0..N

TISSR_OUT_FICUS2-COUNTRY_VAR = TISSR_MARECO-COUNTRY_VAR

TISSR_OUT_FICUS2-CLSNAME = TISSR_OUT_CL-CLSNAME

TISSR_OUT_FICUS2-EVENT = TISSR_OUT_EVT-EVENT

TISSR_OUT_FICUS2-FIELDNAME = TISSR_OUT_FN-FIELDNAME

TISSR_OUT_FICUS2-CMPNAME = TISSR_OUT_FNMT-CMPNAME

TISSR_OUT_FICUS2-LISTTYP = TISSR_OUT_LT-LISTTYP