

SAP ABAP table TRFV_POS_SUBTOT {Generated Table for View TRFV_POS_SUBTOT}

TRFV_POS_SUBTOT
<u>MANDT_CL</u> [CLNT (3)]
<u>CLASS_POS_GUID</u> [CHAR (32)]
<u>COMPANY_CODE</u> [CHAR (4)]
<u>CLASS_ID</u> [CHAR (13)]
<u>POSITION_ACCOUNT</u> [CHAR (10)]
<u>POSITION_CAT</u> [CHAR (1)]
<u>FLAG_MARGIN_REL</u> [CHAR (1)]
<u>STOCK_EXCHANGE</u> [CHAR (10)]
<u>RATE_TYPE</u> [CHAR (2)]
<u>PRODUCT_CATEGORY</u> [NUMC (3)]
<u>ACC_ASS_REF</u> [CHAR (8)]
<u>MANDT_CA</u> [CLNT (3)]
<u>CALC_POS_GUID</u> [CHAR (32)]
<u>LOT</u> [RAW (16)]
<u>FLAG_LONG_SHORT</u> [CHAR (1)]
<u>MANDT_SUB</u> [CLNT (3)]
<u>SUBTOTAL_GUID</u> [CHAR (32)]

T001
<u>MANDT</u> [CLNT (3)]
<u>BUKRS</u> [CHAR (4)]

TRFT_POS_ACCOUNT
<u>MANDT</u> [CLNT (3)]
<u>COMPANY_CODE</u> [CHAR (4)]
<u>POS_ACCOUNT</u> [CHAR (10)]

TW56
<u>MANDT</u> [CLNT (3)]
<u>SKURSART</u> [CHAR (2)]

TWH01
<u>MANDT</u> [CLNT (3)]
<u>RHANDPL</u> [CHAR (10)]

VWPANLA
<u>MANDT</u> [CLNT (3)]
<u>RANL</u> [CHAR (13)]

TRFV_POS_SUBTOT-COMPANY_CODE = T001-BUKRS

TRFV_POS_SUBTOT-POSITION_ACCOUNT = TRFT_POS_ACCOUNT-POS_ACCOUNT

TRFV_POS_SUBTOT-RATE_TYPE = TW56-SKURSART

TRFV_POS_SUBTOT-STOCK_EXCHANGE = TWH01-RHANDPL

TRFV_POS_SUBTOT-CLASS_ID = VWPANLA-RANL