

# SAP ABAP table TRST\_RECON\_POS {Reconciliation Positions}

TRST\_RECON\_POS-MANDT = T000-MANDT

TRST_RECON_POS
<u>MANDT</u> [CLNT (3)]
POSITION_KEY [INT4 (10)]
NUMBERID [NUMC (10)]
SECURITY_ID [CHAR (13)]
POS_CURRENCY [CUKY (5)]
STOCK_EXCHANGE [CHAR (10)]
POS_RECORD_NAME [CHAR (15)]
POS_RECORD_TYPE [CHAR (6)]

T000
<u>MANDT</u> [CLNT (3)]

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

TRSC_RECON_PRT
<u>MANDT</u> [CLNT (3)]
<u>POS_REC_TYPE</u> [CHAR (6)]

TRSC_RECON_RD
<u>MANDT</u> [CLNT (3)]
<u>RECORD_NAME</u> [CHAR (15)]

TRST_RECON_RCE
<u>MANDT</u> [CLNT (3)]
<u>NUMBERID</u> [NUMC (10)]

TWH01
<u>MANDT</u> [CLNT (3)]
<u>RHANDPL</u> [CHAR (10)]

VWPANLA
<u>MANDT</u> [CLNT (3)]
<u>RANL</u> [CHAR (13)]

1

1

1

1

1

1

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

TRST\_RECON\_POS-POS\_RECORD\_TYPE = TRSC\_RECON\_PRT-POS\_REC\_TYPE

TRST\_RECON\_POS-POS\_RECORD\_NAME = TRSC\_RECON\_RD-RECORD\_NAME

TRST\_RECON\_POS-NUMBERID = TRST\_RECON\_RCE-NUMBERID

TRST\_RECON\_POS-STOCK\_EXCHANGE = TWH01-RHANDPL

TRST\_RECON\_POS-SECURITY\_ID = VWPANLA-RANL