

SAP ABAP table UDM_BW_CASE_ATTR {Case Data for BW}

UDM_BW_CASE_ATTR
CASE_TYPE [CHAR (4)]
CREATED_BY [CHAR (12)]
CHANGED_BY [CHAR (12)]
CLOSED_BY [CHAR (12)]
PROCESSOR [CHAR (12)]
RESPONSIBLE [CHAR (12)]
ESCAL_REASON [CHAR (2)]
CATEGORY [CHAR (4)]
PRIORITY [NUMC (1)]
SECURE_LEVEL [CHAR (1)]
PROFILE_ID [CHAR (8)]
STAT_ORDERNO [NUMC (2)]
STAT_PARA [CHAR (3)]
REASON_CODE [CHAR (4)]

SCMGATTR_CATEGO
<u>MANDT</u> [CLNT (3)]
CASE_TYPE [CHAR (4)]
CATEGORY [CHAR (4)]

SCMGATTR_PRIO
<u>MANDT</u> [CLNT (3)]
PRIORITY [NUMC (1)]

SCMGATTR_REASON
<u>MANDT</u> [CLNT (3)]
CASE_TYPE [CHAR (4)]
REASON_CODE [CHAR (4)]

SCMGATTR_SESCAL
<u>MANDT</u> [CLNT (3)]
ESCAL_REASON [CHAR (2)]

SCMGAUT_SECLEVL
<u>MANDT</u> [CLNT (3)]
SECURE_LEVEL [CHAR (1)]

SCMGCASETYPE
<u>CLIENT</u> [CLNT (3)]
CASE_TYPE [CHAR (4)]

SCMGSTAT
STAT_PARA [CHAR (3)]

SCMGSTATPROF
<u>CLIENT</u> [CLNT (3)]
PROFILE_ID [CHAR (8)]

SCMGSTATPROFS
<u>CLIENT</u> [CLNT (3)]
PROFILE_ID [CHAR (8)]
STAT_ORDERNO [NUMC (2)]

USR02
<u>MANDT</u> [CLNT (3)]
BNAME [CHAR (12)]

UDM_BW_CASE_ATTR-CATEGORY = SCMGATTR_CATEGO-CATEGORY

0..N

UDM_BW_CASE_ATTR-PRIORITY = SCMGATTR_PRIO-PRIORITY

0..N

UDM_BW_CASE_ATTR-REASON_CODE = SCMGATTR_REASON-REASON_CODE

0..N

UDM_BW_CASE_ATTR-ESCAL_REASON = SCMGATTR_SESCAL-ESCAL_REASON

0..N

UDM_BW_CASE_ATTR-SECURE_LEVEL = SCMGAUT_SECLEVL-SECURE_LEVEL

0..N

UDM_BW_CASE_ATTR-CASE_TYPE = SCMGCASETYPE-CASE_TYPE

0..N

UDM_BW_CASE_ATTR-STAT_PARA = SCMGSTAT-STAT_PARA

1..N

UDM_BW_CASE_ATTR-PROFILE_ID = SCMGSTATPROF-PROFILE_ID

1

1

UDM_BW_CASE_ATTR-STAT_ORDERNO = SCMGSTATPROFS-STAT_ORDERNO

1..N

UDM_BW_CASE_ATTR-CHANGED_BY = USR02-BNAME

1..N

UDM_BW_CASE_ATTR-CLOSED_BY = USR02-BNAME

0..N

UDM_BW_CASE_ATTR-CREATED_BY = USR02-BNAME

0..N

UDM_BW_CASE_ATTR-PROCESSOR = USR02-BNAME

0..N

UDM_BW_CASE_ATTR-RESPONSIBLE = USR02-BNAME

0..N

0..N

0..N

0..N

0..N

0..N

1

1

1

0..N

0..N

0..N

0..N

0..N