

SAP ABAP table V_CRM_MKTPL_AL02 {Generated Table for View}

V_CRM_MKTPL_AL02
<u>MANDT</u> [CLNT (3)]
ALAPPL [CHAR (5)]
ALRULE [CHAR (10)]
ALUOM [UNIT (3)]
GBPA [CHAR (30)]
GBPA_TAB [CHAR (30)]
PERIV [CHAR (2)]
BP_PROFILE2 [CHAR (30)]
GPA_KEY [CHAR (30)]
GPA [CHAR (30)]

V_CRM_MKTPL_AL02-ALAPPL = CRMC_MKTPL_AL00-ALAPPL

CRMC_MKTPL_AL00
<u>MANDT</u> [CLNT (3)]
ALAPPL [CHAR (5)]

1

V_CRM_MKTPL_AL02-BP_PROFILE2 = DD02L-TABNAME

0..N

DD02L
<u>TABNAME</u> [CHAR (30)]
AS4LOCAL [CHAR (1)]
AS4VERS [NUMC (4)]

1

V_CRM_MKTPL_AL02-GBPA_TAB = DD02L-TABNAME

0..N

1

V_CRM_MKTPL_AL02-GBPA = DD03L-FIELDNAME

1

V_CRM_MKTPL_AL02-GPA = DD03L-FIELDNAME

0..N

1

V_CRM_MKTPL_AL02-GPA_KEY = DD03L-FIELDNAME

0..N

1

V_CRM_MKTPL_AL02-MANDT = T000-MANDT

0..N

DD03L
<u>TABNAME</u> [CHAR (30)]
<u>FIELDNAME</u> [CHAR (30)]
AS4LOCAL [CHAR (1)]
AS4VERS [NUMC (4)]
POSITION [NUMC (4)]

1

V_CRM_MKTPL_AL02-ALUOM = T006-MSEHI

0..N

T000
<u>MANDT</u> [CLNT (3)]

1

V_CRM_MKTPL_AL02-PERIV = T009-PERIV

0..N

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

1

0..N

T009
<u>MANDT</u> [CLNT (3)]
<u>PERIV</u> [CHAR (2)]