

SAP ABAP table V_JSBW_RECL_OBJ {Generated Table for View}

V_JSBW_RECL_OBJ
<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]
<u>VBTP</u> [CHAR (1)]
<u>TRVOG</u> [CHAR (1)]
<u>AUART</u> [CHAR (4)]
<u>AUARTGRP</u> [CHAR (1)]
<u>VBELN_V</u> [CHAR (10)]
<u>POSNR_V</u> [NUMC (6)]
<u>ETENR_V</u> [NUMC (4)]
<u>VBELN_N</u> [CHAR (10)]
<u>POSNR_N</u> [NUMC (6)]
<u>ETENR_N</u> [NUMC (4)]
<u>OBJART_V</u> [CHAR (4)]
<u>OBJART_N</u> [CHAR (4)]

V_JSBW_RECL_OBJ-VBELN_N = JKAK-VBELN

0..N

JKAK

<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]

V_JSBW_RECL_OBJ-VBELN_V = JKAK-VBELN

0..N

JKAP

<u>MANDT</u> [CLNT (3)]
<u>VBELN</u> [CHAR (10)]
<u>POSNR</u> [NUMC (6)]

V_JSBW_RECL_OBJ-POSNR_N = JKAP-POSNR

0..N

V_JSBW_RECL_OBJ-POSNR_V = JKAP-POSNR

0..N

T000

<u>MANDT</u> [CLNT (3)]

V_JSBW_RECL_OBJ-MANDT = T000-MANDT

V_JSBW_RECL_OBJ-AUART = TJAK-AUART

0..N

TJAK

<u>MANDT</u> [CLNT (3)]
<u>AUART</u> [CHAR (4)]

V_JSBW_RECL_OBJ-OBJART_N = TJL11-OBJART

0..N

TJL11

<u>MANDT</u> [CLNT (3)]
<u>OBJART</u> [CHAR (4)]

V_JSBW_RECL_OBJ-OBJART_V = TJL11-OBJART

0..N

0..N