

SAP ABAP table V_PFO_COMT {Generated Table for View}

TPFO_SGT
<u>MANDT</u> [CLNT (3)]
<u>SEG_TYP</u> [CHAR (4)]
<u>TR_FLAG</u> [CHAR (1)]
<u>VERSION</u> [NUMC (6)]

TPFO_ROL
<u>MANDT</u> [CLNT (3)]
<u>ROLE</u> [CHAR (4)]
<u>TR_FLAG</u> [CHAR (1)]
<u>VERSION</u> [NUMC (6)]

TPFO_OBT
<u>MANDT</u> [CLNT (3)]
<u>XOBJTYPE</u> [CHAR (4)]
<u>TR_FLAG</u> [CHAR (1)]
<u>VERSION</u> [NUMC (6)]

V_PFO_COMT
<u>MANDT</u> [CLNT (3)]
<u>COMB</u> [CHAR (4)]
<u>TR_FLAG</u> [CHAR (1)]
<u>VERSION</u> [NUMC (6)]
<u>OBJKIND</u> [CHAR (4)]
<u>OBJTYPE</u> [CHAR (4)]
<u>BUSI_BEGIN</u> [NUMC (14)]
<u>BUSI_END</u> [NUMC (14)]
<u>TECH_BEGIN</u> [NUMC (14)]
<u>TECH_END</u> [NUMC (14)]
<u>FLG_CANCEL_OB</u> [CHAR (1)]
<u>FLG_CANCEL_VERS</u> [CHAR (1)]
<u>CHG_TCODE</u> [CHAR (20)]
<u>CHG_USR</u> [CHAR (12)]
<u>TRI_METH_TYP</u> [CHAR (1)]
<u>TRI_METH_TARGET</u> [CHAR (1)]
<u>STATUS_VERSION</u> [CHAR (1)]
<u>STATUS_WORK</u> [CHAR (1)]
<u>C_OBJKIND</u> [CHAR (4)]
<u>C_OBJTYPE</u> [CHAR (4)]
<u>ROLE</u> [CHAR (4)]
<u>SEG_TYP</u> [CHAR (4)]
<u>DESCR</u> [CHAR (40)]

0..N V_PFO_COMT-STATUS_VERSION = TCACS_VALSTAT1-STATUS_VERSION
0..N V_PFO_COMT-STATUS_WORK = TCACS_VALSTAT1-STATUS_WORK
0..N

TCACS_VALSTAT1
<u>STATUSCLASS</u> [CHAR (1)]
<u>STATUS_VERSION</u> [CHAR (1)]
<u>STATUS_WORK</u> [CHAR (1)]