

SAP ABAP table V_RESBRSADD {Generated Table for View}

V_RESBRSADD
MANDT [CLNT (3)]
RSNUM [NUMC (10)]
RSPOS [NUMC (4)]
RSART [CHAR (1)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
SOBKZ [CHAR (1)]
MEINS [UNIT (3)]
WAERS [CUKY (5)]
ERFME [UNIT (3)]
BNFPO [NUMC (5)]
AUFNR [CHAR (12)]
KDAUF [CHAR (10)]
GSBER [CHAR (4)]
SANKA [CHAR (1)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
EBELE [NUMC (4)]
KNTTP [CHAR (1)]
OBJNR [CHAR (22)]
INFNR [CHAR (10)]

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

EBAN
MANDT [CLNT (3)]
BANFN [CHAR (10)]
BNFPO [NUMC (5)]

EINA
MANDT [CLNT (3)]
INFNR [CHAR (10)]

EKET
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
ETENR [NUMC (4)]

EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

T000
MANDT [CLNT (3)]

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

T148
MANDT [CLNT (3)]
SOBKZ [CHAR (1)]

T163K
MANDT [CLNT (3)]
KNTTP [CHAR (1)]

TCK08
MANDT [CLNT (3)]
SELKZ [CHAR (1)]

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

{0,1} {0,1}

V_RESBRSADD-AUFNR = AUFK-AUFNR 0..N

V_RESBRSADD-BNFPO = EBAN-BNFPO 0..N

V_RESBRSADD-INFNR = EINA-INFNR 0..N

V_RESBRSADD-EBELE = EKET-ETENR 0..N

V_RESBRSADD-EBELN = EKKO-EBELN 0..N

V_RESBRSADD-EBELP = EKPO-EBELP 0..N

V_RESBRSADD-MATNR = MARA-MATNR 0..N

V_RESBRSADD-OBJNR = ONR00-OBJNR 1

V_RESBRSADD-MANDT = T000-MANDT {0,1} 0..N

V_RESBRSADD-WERKS = T001W-WERKS 1 1

V_RESBRSADD-ERFME = T006-MSEHI {0,1} 0..N

V_RESBRSADD-MEINS = T006-MSEHI 1 0..N

V_RESBRSADD-SOBKZ = T148-SOBKZ {0,1} 0..N

V_RESBRSADD-KNTTP = T163K-KNTTP 1 0..N

V_RESBRSADD-SANKA = TCK08-SELKZ {0,1} 0..N

V_RESBRSADD-WAERS = TCURC-WAERS 1 0..N

V_RESBRSADD-GSBER = TGSB-GSBER {0,1} 0..N

V_RESBRSADD-KDAUF = VBUK-VBELN 1 0..N