

# SAP ABAP table V\_T012K {Generated Table for View}

V\_T012K-HKONT = SKB1-SAKNR

V_T012K
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
HBKID [CHAR (5)]
HKTID [CHAR (5)]
BANKS [CHAR (3)]
WAERS [CUKY (5)]
FDGRP [CHAR (10)]
ABWAE [CUKY (5)]
HKONT [CHAR (10)]
WEKON [CHAR (10)]
HBID1 [CHAR (5)]
HKID1 [CHAR (5)]
HBID2 [CHAR (5)]
HKID2 [CHAR (5)]
WKKON [CHAR (10)]
WIKON [CHAR (10)]

SKB1
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SAKNR [CHAR (10)]

T000
MANDT [CLNT (3)]

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]

T012
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
HBKID [CHAR (5)]

T012K
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
HBKID [CHAR (5)]
HKTID [CHAR (5)]

T035
MANDT [CLNT (3)]
GRUPP [CHAR (10)]

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

1 1 1

1

1

1

1

1

1

1

1

1

1

1

1

1

{0,1} {0,1}

1

1

1

1

1

1

1

1

1

1

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

0..N

1..N

V\_T012K-WEKON = SKB1-SAKNR

V\_T012K-WIKON = SKB1-SAKNR

V\_T012K-WKKON = SKB1-SAKNR

V\_T012K-MANDT = T000-MANDT

V\_T012K-BUKRS = T001-BUKRS

V\_T012K-BANKS = T005-LAND1

V\_T012K-HBID1 = T012-HBKID

V\_T012K-HBID2 = T012-HBKID

V\_T012K-HBKID = T012-HBKID

V\_T012K-HKID1 = T012K-HKTID

V\_T012K-HKID2 = T012K-HKTID

V\_T012K-FDGRP = T035-GRUPP

V\_T012K-ABWAE = TCURC-WAERS

V\_T012K-WAERS = TCURC-WAERS