

SAP ABAP table V_T559E {Generated Table for View}

V_T559E
<u>MANDT</u> [CLNT (3)]
MOPGK [CHAR (1)]
MOZKO [NUMC (2)]
MOBDE [NUMC (2)]
<u>QTYPE</u> [NUMC (2)]
<u>RULNO</u> [NUMC (3)]
<u>SEQNR</u> [NUMC (3)]
<u>ENDDA</u> [DATS (8)]
SEUNI [CHAR (3)]
AGUNI [CHAR (3)]
TTZES [CHAR (4)]
TTSAL [CHAR (4)]
NFREQ [NUMC (2)]
BASDT [CHAR (2)]
BASRU [CHAR (3)]

V_T559E-MANDT = T000-MANDT

0..N

T000
<u>MANDT</u> [CLNT (3)]

V_T559E-AGUNI = T538A-ZEINH

0..N

T538A
<u>MANDT</u> [CLNT (3)]
<u>ZEINH</u> [CHAR (3)]

V_T559E-BASRU = T538A-ZEINH

0..N

T548Y
<u>MANDT</u> [CLNT (3)]
<u>DATAR</u> [CHAR (2)]

V_T559E-SEUNI = T538A-ZEINH

0..N

V_T559E-BASDT = T548Y-DATAR

0..N

V_T559E-NFREQ = T549R-PERMO

T549R
<u>MANDT</u> [CLNT (3)]
<u>PERMO</u> [NUMC (2)]

V_T559E-TTSAL = T555A-ZTART

0..N

T555A
<u>MANDT</u> [CLNT (3)]
<u>MOBDE</u> [NUMC (2)]
<u>ZTART</u> [CHAR (4)]
<u>ENDDA</u> [DATS (8)]

V_T559E-TTZES = T555A-ZTART

0..N

V_T559E-QTYPE = T556A-KTART

0..N

T556A
<u>MANDT</u> [CLNT (3)]
<u>MOPGK</u> [CHAR (1)]
<u>MOZKO</u> [NUMC (2)]
<u>KTART</u> [NUMC (2)]
<u>ENDDA</u> [DATS (8)]