

SAP ABAP table V_TCA41_R {Generated Table for View}

V_TCA41_R-MANDT = T000-MANDT

0..N

T000
<u>MANDT</u> [CLNT (3)]

V_TCA41_R-WERKS = T001W-WERKS

0..N

T001W
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]

V_TCA41_R-PLNME = T006-MSEHI

0..N

T006
<u>MANDT</u> [CLNT (3)]
<u>MSEHI</u> [UNIT (3)]

1/{0,1}

V_TCA41_R
<u>MANDT</u> [CLNT (3)]
<u>PLNAW</u> [CHAR (1)]
<u>PROFIDNETZ</u> [CHAR (7)]
<u>PLNME</u> [UNIT (3)]
<u>WERKS</u> [CHAR (4)]
<u>VERWE</u> [CHAR (3)]
<u>STATU</u> [CHAR (3)]
<u>WAERS</u> [CUKY (5)]
<u>ZERMA</u> [CHAR (5)]
<u>GRPRF_GRUP</u> [CHAR (4)]

V_TCA41_R-VERWE = T411-VERWE

0..N

T411
<u>MANDT</u> [CLNT (3)]
<u>VERWE</u> [CHAR (3)]

{0,1}

V_TCA41_R-STATU = T412-PLNST

0..N

T412
<u>MANDT</u> [CLNT (3)]
<u>PLNST</u> [CHAR (3)]

{0,1}

{0,1}

V_TCA41_R-ZERMA = T429-ZERMA

{0,1}

T429
<u>MANDT</u> [CLNT (3)]
<u>WERKS</u> [CHAR (4)]
<u>ZERMA</u> [CHAR (5)]

V_TCA41_R-PLNAW = TCA09-PLNAW

0..N

1

TCA09
<u>MANDT</u> [CLNT (3)]
<u>PLNAW</u> [CHAR (1)]

{0,1}

{0,1}

V_TCA41_R-GRPRF_GRUP = TCNG-PRF_GRUPPE

0..N

TCNG
<u>MANDT</u> [CLNT (3)]
<u>PRF_GRUPPE</u> [CHAR (4)]
<u>PRF_NAME</u> [CHAR (12)]
<u>PRF_INDEX</u> [CHAR (1)]

V_TCA41_R-WAERS = TCURC-WAERS

0..N

TCURC
<u>MANDT</u> [CLNT (3)]
<u>WAERS</u> [CUKY (5)]

0..N