

SAP ABAP table V_TFK2618XX {Generated Table for View}

V_TFK2618XX-MANDT = T000-MANDT

T000
<u>MANDT</u> [CLNT (3)]

V_TFK2618XX
<u>MANDT</u> [CLNT (3)]
<u>APPLK</u> [CHAR (1)]
<u>RNDKEY</u> [CHAR (4)]
<u>HVORG_RD</u> [CHAR (4)]
<u>TVORGS_RD</u> [CHAR (4)]
<u>TVORGH_RD</u> [CHAR (4)]
<u>HVORG_TOL</u> [CHAR (4)]
<u>TVORGS_TOL</u> [CHAR (4)]
<u>TVORGH_TOL</u> [CHAR (4)]
<u>FUNC_RDO</u> [CHAR (30)]
<u>FUNC_RDN</u> [CHAR (30)]

V_TFK2618XX-FUNC_RDN = TFDIR-FUNCNAME
0..N
0..N V_TFK2618XX-FUNC_RDO = TFDIR-FUNCNAME
0..N

TFDIR
<u>FUNCNAME</u> [CHAR (30)]

V_TFK2618XX-HVORG_RD = TFKHVO-HVORG
0..N
0..N V_TFK2618XX-HVORG_TOL = TFKHVO-HVORG
0..N
0..N V_TFK2618XX-TVORGH_RD = TFKTVO-TVORG
0..N

TFKHVO
<u>MANDT</u> [CLNT (3)]
<u>APPLK</u> [CHAR (1)]
<u>HVORG</u> [CHAR (4)]

V_TFK2618XX-TVORGH_TOL = TFKTVO-TVORG
0..N
0..N V_TFK2618XX-TVORGS_RD = TFKTVO-TVORG
0..N
0..N V_TFK2618XX-TVORGS_TOL = TFKTVO-TVORG
0..N

TFKTVO
<u>MANDT</u> [CLNT (3)]
<u>APPLK</u> [CHAR (1)]
<u>HVORG</u> [CHAR (4)]
<u>TVORG</u> [CHAR (4)]