

SAP ABAP table V_WCOCOH_VEN_LST {Generated Table for View}

V_WCOCOH_VEN_LST-CUST_OWNER = KNA1-KUNNR

0..N

KNA1
<u>MANDT</u> [CLNT (3)]
KUNNR [CHAR (10)]

V_WCOCOH_VEN_LST-VEND_OWNER = LFA1-LIFNR

0..N

LFA1
<u>MANDT</u> [CLNT (3)]
LIFNR [CHAR (10)]

V_WCOCOH_VEN_LST-CLIENT = T000-MANDT

0..N

T000
<u>MANDT</u> [CLNT (3)]

V_WCOCOH_VEN_LST-EKGRP = T024-EKGRP

0..N

T024
<u>MANDT</u> [CLNT (3)]
EKGRP [CHAR (3)]

V_WCOCOH_VEN_LST-EKORG = T024E-EKORG

0..N

T024E
<u>MANDT</u> [CLNT (3)]
EKORG [CHAR (4)]

V_WCOCOH_VEN_LST-CC_CURR = TCURC-WAERS

0..N

TCURC
<u>MANDT</u> [CLNT (3)]
WAERS [CUKY (5)]

V_WCOCOH_VEN_LST-RATE_TYPE = TCURV-KURST

0..N

TCURV
<u>MANDT</u> [CLNT (3)]
KURST [CHAR (4)]

V_WCOCOH_VEN_LST-SPART = TSPA-SPART

V_WCOCOH_VEN_LST-VKBUR = TVBUR-VKBUR

0..N

TSPA
<u>MANDT</u> [CLNT (3)]
SPART [CHAR (2)]

V_WCOCOH_VEN_LST-VKGRP = TVBVK-VKGRP

0..N

TVBUR
<u>MANDT</u> [CLNT (3)]
VKBUR [CHAR (4)]

V_WCOCOH_VEN_LST-VKORG = TVKO-VKORG

0..N

TVBVK
<u>MANDT</u> [CLNT (3)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]

V_WCOCOH_VEN_LST-VTWEG = TVTW-VTWEG

0..N

TVKO
<u>MANDT</u> [CLNT (3)]
VKORG [CHAR (4)]

V_WCOCOH_VEN_LST-CONTRACT_TYPE = TWCBCONTRTYPE-CONTRACT_TYPE

0..N

TWCBCONTRTYPE
<u>CLIENT</u> [CLNT (3)]
CONTRACT_TYPE [CHAR (4)]

V_WCOCOH_VEN_LST
<u>CLIENT</u> [CLNT (3)]
NUM [CHAR (10)]
CONTRACT_TYPE [CHAR (4)]
VEND_OWNER [CHAR (10)]
CUST_OWNER [CHAR (10)]
EKORG [CHAR (4)]
EKGRP [CHAR (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
CC_CURR [CUKY (5)]
RATE_TYPE [CHAR (4)]
VKGRP [CHAR (3)]
VKBUR [CHAR (4)]

1

1

1

0..N

1

1

1

1

1

1

1

1

1