

SAP ABAP table VBAPVB_LOC {Reference Structure for XVBAP/YVBAP + Location Data}

VBAPVB_LOC-AUFNR = AUFK-AUFNR			0..N	AUFK MANDT [CLNT (3)] AUFNR [CHAR (12)]
VBAPVB_LOC-FERC_IND = FERC_C7-IND			0..N	FERC_C7 MANDT [CLNT (3)] IND [CHAR (4)]
VBAPVB_LOC-J_1BCFOP = J_1BAG-CFOP			0..N	J_1BAG MANDT [CLNT (3)] CFOP [CHAR (10)]
VBAPVB_LOC-J_1BTAXLW1 = J_1BATL1-TAXLAW			0..N	J_1BATL1 MANDT [CLNT (3)] TAXLAW [CHAR (3)]
VBAPVB_LOC-J_1BTAXLW2 = J_1BATL2-TAXLAW			0..N	J_1BATL2 MANDT [CLNT (3)] TAXLAW [CHAR (3)]
VBAPVB_LOC-J_1BTAXLW3 = J_1BATL3-TAXLAW			0..N	J_1BATL3 MANDT [CLNT (3)] TAXLAW [CHAR (3)]
VBAPVB_LOC-J_1BTAXLW4 = J_1BATL4A-TAXLAW			0..N	J_1BATL4A MANDT [CLNT (3)] TAXLAW [CHAR (3)]
VBAPVB_LOC-J_1BTAXLW5 = J_1BATL5-TAXLAW			0..N	J_1BATL5 MANDT [CLNT (3)] TAXLAW [CHAR (3)]
VBAPVB_LOC-J_1BTXSDC = J_1BTXSDC-TAXCODE			0..N	J_1BTXSDC MANDT [CLNT (3)] TAXCODE [CHAR (2)]
VBAPVB_LOC-CLINT = KLAH-CLINT			0..N	KLAH MANDT [CLNT (3)] CLINT [NUMC (10)]
VBAPVB_LOC-KNUMA_AG = KONA-KNUMA			0..N	KONA MANDT [CLNT (3)] KNUMA [CHAR (10)]
VBAPVB_LOC-KNUMA_PI = KONA-KNUMA			0..N	KONA MANDT [CLNT (3)] KNUMA [CHAR (10)]
VBAPVB_LOC-MATNR = MARA-MATNR			0..N	MARA MANDT [CLNT (3)] MATNR [CHAR (18)]
VBAPVB_LOC-MATWA = MARA-MATNR			0..N	MARA MANDT [CLNT (3)] MATNR [CHAR (18)]
VBAPVB_LOC-PMATN = MARA-MATNR			0..N	MCHA MANDT [CLNT (3)] MATNR [CHAR (18)] WERKS [CHAR (4)] CHARG [CHAR (10)]
VBAPVB_LOC-UPMAT = MARA-MATNR			0..N	MCHA MANDT [CLNT (3)] MATNR [CHAR (18)] WERKS [CHAR (4)] CHARG [CHAR (10)]
VBAPVB_LOC-VPMAT = MARA-MATNR			0..N	MCHA MANDT [CLNT (3)] MATNR [CHAR (18)] WERKS [CHAR (4)] CHARG [CHAR (10)]
VBAPVB_LOC-CHARG = MCHA-CHARG			0..N	MSR_C_RET_REASON MANDT [CLNT (3)] RET_REASON [CHAR (3)]
VBAPVB_LOC-MSR_RET_REASON = MSR_C_RET_REASON-RET_REASON			0..N	MSR_C_RET_REASON MANDT [CLNT (3)] RET_REASON [CHAR (3)]
VBAPVB_LOC-MSR_REFUND_CODE = MSR_C_RET_REFUND-RETURNS_REFUND			0..N	MSR_C_RET_REFUND MANDT [CLNT (3)] RETURNS_REFUND [CHAR (3)]
VBAPVB_LOC-OBJNR = ONR00-OBJNR			0..N	ONR00 MANDT [CLNT (3)] OBJNR [CHAR (22)]
VBAPVB_LOC-PS_PSP_PNR = PRPS-PSPNR			0..N	PRPS MANDT [CLNT (3)] PSPNR [NUMC (8)]
VBAPVB_LOC-SERNR = SNUM-SERNR			0..N	SNUM MANDT [CLNT (3)] SERNR [CHAR (8)]
VBAPVB_LOC-MANDT = T000-MANDT			0..N	T000 MANDT [CLNT (3)]
VBAPVB_LOC-LGORT = T001L-LGORT			0..N	T001L MANDT [CLNT (3)] WERKS [CHAR (4)] LGORT [CHAR (4)]
VBAPVB_LOC-VPWRK = T001W-WERKS			0..N	T001W MANDT [CLNT (3)] WERKS [CHAR (4)]
VBAPVB_LOC-GEWEI = T006-MSEHI			0..N	T006 MANDT [CLNT (3)] GEWEI [UNIT (3)]
VBAPVB_LOC-KMEIN = T006-MSEHI			0..N	T006 MANDT [CLNT (3)] GEWEI [UNIT (3)]
VBAPVB_LOC-MEINS = T006-MSEHI			0..N	T006 MANDT [CLNT (3)] GEWEI [UNIT (3)]
VBAPVB_LOC-PRBME = T006-MSEHI			0..N	T023 MANDT [CLNT (3)] MATKL [CHAR (9)]
VBAPVB_LOC-VOLEH = T006-MSEHI			0..N	T023 MANDT [CLNT (3)] MATKL [CHAR (9)]
VBAPVB_LOC-VRKME = T006-MSEHI			0..N	T148 MANDT [CLNT (3)] SOBKZ [CHAR (1)]
VBAPVB_LOC-ZIEME = T006-MSEHI			0..N	T148 MANDT [CLNT (3)] SOBKZ [CHAR (1)]
VBAPVB_LOC-MATKL = T023-MATKL			0..N	T148 MANDT [CLNT (3)] SOBKZ [CHAR (1)]
VBAPVB_LOC-SOBKZ = T148-SOBKZ			0..N	T148 MANDT [CLNT (3)] SOBKZ [CHAR (1)]
VBAPVB_LOC-BWTAR = T149D-BWTAR			0..N	T149D MANDT [CLNT (3)] BWTAR [CHAR (10)]
VBAPVB_LOC-KNTTP = T163K-KNTTP			0..N	T163K MANDT [CLNT (3)] KNTTP [CHAR (1)]
VBAPVB_LOC-KONDM = T178-KONDM			0..N	T178 MANDT [CLNT (3)] KONDM [CHAR (2)]
VBAPVB_LOC-UKONM = T178-KONDM			0..N	T178 MANDT [CLNT (3)] KONDM [CHAR (2)]
VBAPVB_LOC-PRODH = T179-PRODH			0..N	T179 MANDT [CLNT (3)] PRODH [CHAR (18)]
VBAPVB_LOC-KOSCH = T190S-KOSCH			0..N	T190S MANDT [CLNT (3)] KOSCH [CHAR (18)]
VBAPVB_LOC-SERAIL = T377P-SERAIL			0..N	T377P MANDT [CLNT (3)] SERAIL [CHAR (4)]
VBAPVB_LOC-BEDAE = T459A-BEDAE			0..N	T459A MANDT [CLNT (3)] BEDAE [CHAR (4)]
VBAPVB_LOC-EXART = T605-EXART			0..N	T605 MANDT [CLNT (3)] LANDI [CHAR (3)] EXART [CHAR (2)]
VBAPVB_LOC-KALSM_K = T683-KALSM			0..N	T683 MANDT [CLNT (3)] KVWEV [CHAR (1)] KAPPL [CHAR (2)] KALSM [CHAR (6)]
VBAPVB_LOC-ABFOR = T691K-ABSFO			0..N	T691K MANDT [CLNT (3)] ABSFO [CHAR (2)]
VBAPVB_LOC-LOGSYS = TBDLS-LOGSYS			0..N	TBDLS LOGSYS [CHAR (10)]
VBAPVB_LOC-KALVAR = TCK03-KLVAR			0..N	TCK03 MANDT [CLNT (3)] KLVAR [CHAR (4)]
VBAPVB_LOC-WAERK = TCURC-WAERS			0..N	TCURC MANDT [CLNT (3)] WAERS [CHAR (5)]
VBAPVB_LOC-GSBER = TGSB-GSBER			0..N	TGSB MANDT [CLNT (3)] GSBER [CHAR (4)]
VBAPVB_LOC-ABGRS = TKKAA-ABGSL			0..N	TKKAA MANDT [CLNT (3)] ABGSL [CHAR (6)]
VBAPVB_LOC-MFRGR = TMFG-MFRGR			0..N	TMFG MANDT [CLNT (3)] MFRGR [CHAR (8)]
VBAPVB_LOC-MTVFP = TMVF-MTVFP			0..N	TMVF MANDT [CLNT (3)] MTVFP [CHAR (2)]
VBAPVB_LOC-LPRIO = TPRI0-LPRIO			0..N	TPRIO MANDT [CLNT (3)] LPRIO [NUMC (2)]
VBAPVB_LOC-PVHKN = TPVH-PVHKN			0..N	TPVH MANDT [CLNT (3)] PVHKN [CHAR (1)]
VBAPVB_LOC-SPART = TSPA-SPART			0..N	TSPA MANDT [CLNT (3)] SPART [CHAR (2)]
VBAPVB_LOC-ABGRU = TVAG-ABGRU			0..N	TVAG MANDT [CLNT (3)] ABGRU [CHAR (2)]
VBAPVB_LOC-BONUS = TVBO-BONUS			0..N	TVBO MANDT [CLNT (3)] BONUS [CHAR (2)]
VBAPVB_LOC-MAGRV = TVEGR-MAGRV			0..N	TVEGR MANDT [CLNT (3)] MAGRV [CHAR (4)]
VBAPVB_LOC-FAKSP = TVFS-FAKSP			0..N	TVFS MANDT [CLNT (3)] FAKSP [CHAR (2)]
VBAPVB_LOC-KTGRM = TVKM-KTGRM			0..N	TVKM MANDT [CLNT (3)] KTGRM [CHAR (2)]
VBAPVB_LOC-VKAUS = TVLV-ABRVW			0..N	TVLV MANDT [CLNT (3)] ABRVW [CHAR (3)]
VBAPVB_LOC-MVGR1 = TVM1-MVGR1			0..N	TVM1 MANDT [CLNT (3)] MVGR1 [CHAR (3)]
VBAPVB_LOC-MVGR2 = TVM2-MVGR2			0..N	TVM2 MANDT [CLNT (3)] MVGR2 [CHAR (3)]
VBAPVB_LOC-MVGR3 = TVM3-MVGR3			0..N	TVM3 MANDT [CLNT (3)] MVGR3 [CHAR (3)]
VBAPVB_LOC-MVGR4 = TVM4-MVGR4			0..N	TVM4 MANDT [CLNT (3)] MVGR4 [CHAR (3)]
VBAPVB_LOC-MVGR5 = TVM5-MVGR5			0..N	TVM5 MANDT [CLNT (3)] MVGR5 [CHAR (3)]
VBAPVB_LOC-PROVG = TVPR-PROVG			0..N	TVPR MANDT [CLNT (3)] PROVG [CHAR (2)]
VBAPVB_LOC-PSTYV = TVPT-PSTYV			0..N	TVPT MANDT [CLNT (3)] PSTYV [CHAR (4)]
VBAPVB_LOC-VKGRU = TVRMAVK-VORGA			0..N	TVRMAVK MANDT [CLNT (3)] VORGA [CHAR (3)]
VBAPVB_LOC-ROUTE = TVRO-ROUTE			0..N	TVRO MANDT [CLNT (3)] ROUTE [CHAR (6)]
VBAPVB_LOC-VSTEL = TVST-VSTEL			0..N	TVST MANDT [CLNT (3)] VSTEL [CHAR (4)]
VBAPVB_LOC-SUGRD = TVSU-SUGRD			0..N	TVSU MANDT [CLNT (3)] SUGRD [CHAR (4)]
VBAPVB_LOC-PLAVO = TVZP-PLAVO			0..N	TVZP MANDT [CLNT (3)] SUGRD [CHAR (4)]
VBAPVB_LOC-VBELN = VBUK-VBELN			0..N	TVZP MANDT [CLNT (3)] PLAVO [CHAR (4)]
VBAPVB_LOC-VGBEL = VBUK-VBELN			0..N	TVZP MANDT [CLNT (3)] PLAVO [CHAR (4)]
VBAPVB_LOC-WKTNR = VBUK-VBELN			0..N	VBUK MANDT [CLNT (3)] VBELN [CHAR (10)]
VBAPVB_LOC-POSNR = VBUP-POSNR			0..N	VBUK MANDT [CLNT (3)] VBELN [CHAR (10)]
VBAPVB_LOC-POSNV = VBUP-POSNR			0..N	VBUK MANDT [CLNT (3)] VBELN [CHAR (10)]
VBAPVB_LOC-VGPOS = VBUP-POSNR			0..N	VBUK MANDT [CLNT (3)] VBELN [CHAR (10)]
VBAPVB_LOC-WKTPS = VBUP-POSNR			0..N	VBUK MANDT [CLNT (3)] VBELN [CHAR (10)]
VBAPVB_LOC-SKOPF = WSOH-SKOPF			0..N	WSOH MANDT [CLNT (3)] SKOPF [CHAR (18)]