

# SAP ABAP table VFPRCC\_PRCE2VIEW {Pricing Elements to View Mapping}

VFPRCC\_PRCE2VIEW-CLIENT = T000-MANDT

<b>VFPRCC_PRCE2VIEW</b>
<u>CLIENT</u> [CLNT (3)]
<u>VIEW_ID</u> [NUMC (4)]
<u>KAPPL</u> [CHAR (2)]
<u>KALSM</u> [CHAR (6)]
<u>STUNR</u> [NUMC (3)]
<u>COND_TYPE</u> [CHAR (4)]

<b>T000</b>
<u>MANDT</u> [CLNT (3)]

<b>T681A</b>
<u>KAPPL</u> [CHAR (2)]

<b>T683</b>
<u>MANDT</u> [CLNT (3)]
<u>KVEWE</u> [CHAR (1)]
<u>KAPPL</u> [CHAR (2)]
<u>KALSM</u> [CHAR (6)]

<b>T683S</b>
<u>MANDT</u> [CLNT (3)]
<u>KVEWE</u> [CHAR (1)]
<u>KAPPL</u> [CHAR (2)]
<u>KALSM</u> [CHAR (6)]
<u>STUNR</u> [NUMC (3)]
<u>ZAEHK</u> [NUMC (2)]

<b>T685A</b>
<u>MANDT</u> [CLNT (3)]
<u>KAPPL</u> [CHAR (2)]
<u>KSCHL</u> [CHAR (4)]

<b>VFPRCC_VIEW_REG</b>
<u>CLIENT</u> [CLNT (3)]
<u>VIEW_ID</u> [NUMC (4)]

1

1

0..N

0..N

1

1

0..N

0..N

0..N

0..N

0..N

0..N

VFPRCC\_PRCE2VIEW-KAPPL = T681A-KAPPL

VFPRCC\_PRCE2VIEW-KALSM = T683-KALSM

VFPRCC\_PRCE2VIEW-STUNR = T683S-STUNR

VFPRCC\_PRCE2VIEW-COND\_TYPE = T685A-KSCHL

VFPRCC\_PRCE2VIEW-VIEW\_ID = VFPRCC\_VIEW\_REG-VIEW\_ID