

SAP ABAP table VIMPLA {Generated Table for View}

VIMPLA
<u>MANDT</u> [CLNT (3)]
WARPL [CHAR (12)]
ERKNZ [CHAR (1)]
AEKNZ [CHAR (1)]
ERSDT [DATS (8)]
ERNAM [CHAR (12)]
AEDAT [DATS (8)]
AENAM [CHAR (12)]
WPTXT [CHAR (40)]
STRAT [CHAR (6)]
ABRHQ [NUMC (3)]
KUNUM [CHAR (10)]
LTKNZ [CHAR (1)]
LVORM [CHAR (1)]
ANZPS [NUMC (4)]
ABNUM [INT4 (10)]
LANGU [LANG (1)]
VSPOS [NUMC (3)]
VSNEG [NUMC (3)]
TOPOS [NUMC (3)]
TONEG [NUMC (3)]
SFAKT [DEC (3)]
STICH [CHAR (1)]
TGOON [NUMC (3)]
HORIZ [NUMC (3)]
HORIZ_DAYS [NUMC (3)]
HORIZ_QUALIFIER [CHAR (1)]
ANDOR [CHAR (1)]
KNAUT [CHAR (1)]
BEGRU [CHAR (4)]
OBJNR [CHAR (22)]
MPTYP [CHAR (2)]
HUNIT [UNIT (3)]
STADI [DATS (8)]
SZAEH [CHAR (22)]
CALL_CONFIRM [CHAR (1)]
PLAN_SORT [CHAR (20)]
FABKL [CHAR (2)]
PUFFP [NUMC (3)]
PUFFN [NUMC (3)]
START_DATE [DATS (8)]
START_TIME [TMS (6)]
CALL_UPDATE_IND [CHAR (1)]
IND_MPLA_API [CHAR (2)]
MCP_SE [CHAR (1)]
WAPOS [CHAR (16)]
WSTRA [CHAR (6)]
EQUNR [CHAR (18)]
PLNTY [CHAR (1)]
WPGRP [CHAR (3)]
GEWRK [NUMC (8)]
IWERK [CHAR (4)]
ILOAN [CHAR (12)]
LAUFN [CHAR (12)]
BAUTL [CHAR (18)]
AUART [CHAR (4)]
ILART [CHAR (3)]
GSBER [CHAR (4)]
MITYP [CHAR (2)]
WAERS [CUKY (5)]
SERMAT [CHAR (18)]
QMNUM [CHAR (12)]
QMART [CHAR (2)]
PRIOK [CHAR (1)]
POS_OBJNR [CHAR (22)]
TPLNR [CHAR (30)]
ABCKZ [CHAR (1)]
SWERK [CHAR (4)]
STORT [CHAR (10)]
BEBER [CHAR (3)]
PPSID [NUMC (8)]
KOKRS [NUMC (4)]
KOSTL [CHAR (10)]
PROID [NUMC (8)]
BUKRS [CHAR (4)]
ANLNR [CHAR (12)]
ANLUN [CHAR (4)]
DAUFN [CHAR (12)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
ADRNR [CHAR (10)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]
IGSBER [CHAR (4)]
IAUFNR [CHAR (12)]

VIMPLA-ADRNR = ADRC-ADDRNUMBER

ADRC
<u>CLIENT</u> [CLNT (3)]
ADDRNUMBER [CHAR (10)]
DATE_FROM [DATS (8)]
NATION [CHAR (1)]

VIMPLA-ANLUN = ANLA-ANLN2

ANLA
<u>MANDT</u> [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]

VIMPLA-ANLNR = ANLH-ANLN1

ANLH
<u>MANDT</u> [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

VIMPLA-DAUFN = AUFK-AUFNR

AUFK
<u>MANDT</u> [CLNT (3)]
AUFNR [CHAR (12)]

VIMPLA-IAUFNR = AUFK-AUFNR

VIMPLA-LAUFN = AUFK-AUFNR

VIMPLA-GEWRK = CRID-OBJID

CRID
<u>MANDT</u> [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

VIMPLA-PPSID = CRID-OBJID

VIMPLA-KOSTL = CSKS-KOSTL

CSKS
<u>MANDT</u> [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

VIMPLA-EQUNR = EQUI-EQUNR

EQUI
<u>MANDT</u> [CLNT (3)]
EQUNR [CHAR (18)]

VIMPLA-TPLNR = IFLOT-TPLNR

IFLOT
<u>MANDT</u> [CLNT (3)]
TPLNR [CHAR (30)]

VIMPLA-ILOAN = ILOA-ILOAN

ILOA
<u>MANDT</u> [CLNT (3)]
ILOAN [CHAR (12)]

VIMPLA-BAUTL = MARA-MATNR

VIMPLA-SERMAT = MARA-MATNR

MARA
<u>MANDT</u> [CLNT (3)]
MATNR [CHAR (18)]

VIMPLA-POS_OBJNR = ONR00-OBJNR

ONR00
<u>MANDT</u> [CLNT (3)]
OBJNR [CHAR (22)]

VIMPLA-PROID = PRPS-PSPNR

PRPS
<u>MANDT</u> [CLNT (3)]
PSPNR [NUMC (8)]

VIMPLA-QMNUM = QMEL-QMNUM

QMEL
<u>MANDT</u> [CLNT (3)]
QMNUM [CHAR (12)]

VIMPLA-MANDT = T000-MANDT

T000
<u>MANDT</u> [CLNT (3)]

VIMPLA-BUKRS = T001-BUKRS

T001
<u>MANDT</u> [CLNT (3)]
BUKRS [CHAR (4)]

VIMPLA-SWERK = T001W-WERKS

T001W
<u>MANDT</u> [CLNT (3)]
WERKS [CHAR (4)]

VIMPLA-AUART = T003O-AUART

T003O
<u>CLIENT</u> [CLNT (3)]
AUART [CHAR (4)]

VIMPLA-WPGRP = T024I-INGRP

T024I
<u>MANDT</u> [CLNT (3)]
IWERK [CHAR (4)]
INGRE [CHAR (3)]

VIMPLA-STRAT = T351-STRAT

VIMPLA-WSTRA = T351-STRAT

VIMPLA-ILART = T353I-ILART

T351
<u>MANDT</u> [CLNT (3)]
STRAT [CHAR (6)]

VIMPLA-PRIOK = T356-PRIOK

T353I
<u>MANDT</u> [CLNT (3)]
ILART [CHAR (3)]

VIMPLA-BEBER = T357-BEBER

T356
<u>MANDT</u> [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

VIMPLA-BEGRU = T370B-BEGRU

T357
<u>MANDT</u> [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

VIMPLA-ABCKZ = T370C-ABCKZ

T370B
<u>MANDT</u> [CLNT (3)]
BEGRU [CHAR (4)]

VIMPLA-PLAN_SORT = T399G-PLAN_SORT

T370C
<u>MANDT</u> [CLNT (3)]
ABCKZ [CHAR (1)]

VIMPLA-IWERK = T399I-IWERK

T399G
<u>MANDT</u> [CLNT (3)]
PLAN_SORT [CHAR (20)]

VIMPLA-MITYP = T399P-MITYP

T399I
<u>MANDT</u> [CLNT (3)]
IWERK [CHAR (4)]

VIMPLA-MPTYP = T399W-MPTYP

T399P
<u>MANDT</u> [CLNT (3)]
MITYP [CHAR (2)]

VIMPLA-STORT = T499S-STAND

T399W
<u>MANDT</u> [CLNT (3)]
MPTYP [CHAR (2)]

VIMPLA-PLNTY = TCA01-PLNTY

T499S
<u>MANDT</u> [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

VIMPLA-WAERS = TCURC-WAERS

TCA01
<u>MANDT</u> [CLNT (3)]
PLNTY [CHAR (1)]

VIMPLA-FABKL = TFACD-IDENT

TCURC
<u>MANDT</u> [CLNT (3)]
WAERS [CUKY (5)]

VIMPLA-GSBER = TGSB-GSBER

TFACD
<u>IDENT</u> [CHAR (2)]

VIMPLA-IGSBER = TGSB-GSBER

VIMPLA-KOKRS = TKA01-KOKRS

TGSB
<u>MANDT</u> [CLNT (3)]
GSBER [CHAR (4)]

VIMPLA-QMART = TQ80-QMART

TKA01
<u>MANDT</u> [CLNT (3)]
KOKRS [CHAR (4)]

VIMPLA-VKGRP = TVBVK-VKGRP

TQ80
<u>MANDT</u> [CLNT (3)]
QMART [CHAR (2)]

VIMPLA-VKBUR = TVKBZ-VKBUR

TVBVK
<u>MANDT</u> [CLNT (3)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]

VIMPLA-VKORG = TVKO-VKORG

TVKBZ
<u>MANDT</u> [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VKBUR [CHAR (4)]

VIMPLA-VTWEG = TVKOV-VTWEG

TVKO
<u>MANDT</u> [CLNT (3)]
VKORG [CHAR (4)]

VIMPLA-SPART = TVTA-SPART

TVKOV
<u>MANDT</u> [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]

TVTA
<u>MANDT</u> [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]