

# SAP ABAP table VV\_CACS\_CASSGN3 {Generated Table for View}

| VV_CACS_CASSGN3                  |
|----------------------------------|
| <u>MANDT</u> [CLNT (3)]          |
| <u>APPL</u> [CHAR (6)]           |
| <u>COMBTP_ID</u> [CHAR (12)]     |
| TABNAME [CHAR (30)]              |
| <u>SEL_ID</u> [NUMC (12)]        |
| <u>PL_SEL_ID</u> [CHAR (10)]     |
| <u>CTRT_TYPE</u> [CHAR (3)]      |
| <u>CTRTST_ID</u> [CHAR (20)]     |
| <u>VERSION</u> [NUMC (6)]        |
| <u>STATUS_VERSION</u> [CHAR (1)] |
| <u>STATUS_WORK</u> [CHAR (1)]    |

| CACS_COMB                    |
|------------------------------|
| <u>MANDT</u> [CLNT (3)]      |
| <u>APPL</u> [CHAR (6)]       |
| <u>COMBTP_ID</u> [CHAR (12)] |
| <u>VERSION</u> [NUMC (6)]    |

| T000                    |
|-------------------------|
| <u>MANDT</u> [CLNT (3)] |

| TCACS_APPLDEF          |
|------------------------|
| <u>APPL</u> [CHAR (6)] |

| TCACS_VALSTAT1                   |
|----------------------------------|
| <u>STATUSCLASS</u> [CHAR (1)]    |
| <u>STATUS_VERSION</u> [CHAR (1)] |
| <u>STATUS_WORK</u> [CHAR (1)]    |

VV\_CACS\_CASSGN3-COMBTP\_ID = CACS\_COMB-COMBTP\_ID 0..N

VV\_CACS\_CASSGN3-MANDT = T000-MANDT 0..N

VV\_CACS\_CASSGN3-APPL = TCACS\_APPLDEF-APPL 0..N

VV\_CACS\_CASSGN3-STATUS\_VERSION = TCACS\_VALSTAT1-STATUS\_VERSION 0..N

VV\_CACS\_CASSGN3-STATUS\_WORK = TCACS\_VALSTAT1-STATUS\_WORK 0..N