

SAP ABAP table VZZKOPO_UPDATE {Condition Items with Update Indicator}

VZZKOPO_UPDATE
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SKOART [NUMC (4)]
SWHRKOND [CUKY (5)]
SBASIS [CHAR (4)]
SZSREF [CHAR (10)]
MWSKZ [CHAR (2)]
KUNNR [CHAR (10)]
ZLSCH [CHAR (1)]
MABER [CHAR (2)]
SPARTNR [CHAR (10)]
SKALID [CHAR (2)]
SZEGEN [NUMC (2)]
SBUST [NUMC (2)]
SKOPO [NUMC (2)]
SFORMREF [CHAR (4)]
SKALID2 [CHAR (2)]
SZWKEY [CHAR (2)]
MANSP [CHAR (1)]
ZAHLS [CHAR (1)]
SFLART [NUMC (4)]
LIFNR [CHAR (10)]
ZLSPR [CHAR (1)]

VZZKOPO_UPDATE-SFORMREF = AT30-RFORMBEZ

AT30
RFORMBEZ [CHAR (4)]

VZZKOPO_UPDATE-SPARTNR = BUT000-PARTNER

BUT000
CLIENT [CLNT (3)]
PARTNER [CHAR (10)]

VZZKOPO_UPDATE-KUNNR = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

VZZKOPO_UPDATE-LIFNR = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

VZZKOPO_UPDATE-MANDT = T000-MANDT

T000
MANDT [CLNT (3)]

VZZKOPO_UPDATE-BUKRS = T001-BUKRS

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

VZZKOPO_UPDATE-MWSKZ = T007A-MWSKZ

T007A
MANDT [CLNT (3)]
KALSM [CHAR (6)]
MWSKZ [CHAR (2)]

VZZKOPO_UPDATE-ZAHLS = T008-ZAHLS

T008
MANDT [CLNT (3)]
ZAHLS [CHAR (1)]

VZZKOPO_UPDATE-ZLSPR = T008-ZAHLS

T040S
MANDT [CLNT (3)]
MANSP [CHAR (1)]

VZZKOPO_UPDATE-MANSP = T040S-MANSP

T042Z
MANDT [CLNT (3)]
LANDI [CHAR (3)]
ZLSCH [CHAR (1)]

VZZKOPO_UPDATE-ZLSCH = T042Z-ZLSCH

T047M
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
MABER [CHAR (2)]

VZZKOPO_UPDATE-MABER = T047M-MABER

VZZKOPO_UPDATE-SZSREF = T056R-REFERENZ

T056R
MANDT [CLNT (3)]
REFERENZ [CHAR (10)]

VZZKOPO_UPDATE-SWHRKOND = TCURC-WAERS

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

VZZKOPO_UPDATE-SZEGEN = TD21-SZEGEN

TD21
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SZEGEN [NUMC (2)]

VZZKOPO_UPDATE-SZWKEY = TDZW-SZWKEY

TDZW
MANDT [CLNT (3)]
SZWKEY [CHAR (2)]

VZZKOPO_UPDATE-SKALID = TFACD-IDENT

TFACD
IDENT [CHAR (2)]

VZZKOPO_UPDATE-SKALID2 = TFACD-IDENT

TIV08
MANDT [CLNT (3)]
SFLART [NUMC (4)]

VZZKOPO_UPDATE-SFLART = TIV08-SFLART

VZZKOPO_UPDATE-SBUST = TZB09-SBUST

TZB09
RANTYP [CHAR (1)]
SBUST [NUMC (2)]

VZZKOPO_UPDATE-SBASIS = TZFB-SBASIS

TZFB
RANTYP [CHAR (1)]
SBASIS [CHAR (4)]

VZZKOPO_UPDATE-SKOART = TZK01-SKOART

TZK01
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SKOART [NUMC (4)]

VZZKOPO_UPDATE-SKOPO = TZK07-SKOPO

TZK07
MANDT [CLNT (3)]
RANTYP [CHAR (1)]
SKOART [NUMC (4)]
SKOPO [NUMC (2)]