

SAP ABAP table WDR_ADP_EVENT_MP {Web Dynpro Runtime: Adapter Event}

WDR_ADP_EVENT_MP
<u>LIBRARY_NAME</u> [CHAR (30)]
<u>ADAPTER_NAME</u> [CHAR (23)]
<u>PROPERTY_NAME</u> [CHAR (30)]
<u>VELEM_LIB_NAME</u> [CHAR (30)]
<u>VELEM_DEF_NAME</u> [CHAR (30)]
<u>VELEM_EVENT_NAME</u> [CHAR (30)]
<u>MAP_LIB_NAME</u> [CHAR (30)]
<u>MAP_DEF_NAME</u> [CHAR (60)]
<u>MAP_PROPERTY</u> [CHAR (60)]

WDR_ADAPTER_PROP
<u>LIBRARY_NAME</u> [CHAR (30)]
<u>ADAPTER_NAME</u> [CHAR (23)]
<u>PROPERTY_NAME</u> [CHAR (30)]

WDY_UI_EVENT_DEF
<u>LIBRARY_NAME</u> [CHAR (30)]
<u>DEFINITION_NAME</u> [CHAR (30)]
<u>EVENT_NAME</u> [CHAR (30)]

WDY_UI_PROP_DEF
<u>LIBRARY_NAME</u> [CHAR (30)]
<u>DEFINITION_NAME</u> [CHAR (60)]
<u>PROPERTY_NAME</u> [CHAR (60)]

WDR_ADP_EVENT_MP-ADAPTER_NAME = WDR_ADAPTER_PROP-LIBRARY_NAME

0..N

WDR_ADP_EVENT_MP-PROPERTY_NAME = WDR_ADAPTER_PROP-ADAPTER_NAME

0..N

WDR_ADP_EVENT_MP-VELEM_DEF_NAME = WDY_UI_EVENT_DEF-DEFINITION_NAME

0..N

WDR_ADP_EVENT_MP-VELEM_EVENT_NAME = WDY_UI_EVENT_DEF-EVENT_NAME

0..N

WDR_ADP_EVENT_MP-VELEM_LIB_NAME = WDY_UI_EVENT_DEF-LIBRARY_NAME

0..N

WDR_ADP_EVENT_MP-MAP_DEF_NAME = WDY_UI_PROP_DEF-DEFINITION_NAME

0..N

WDR_ADP_EVENT_MP-MAP_LIB_NAME = WDY_UI_PROP_DEF-LIBRARY_NAME

0..N

WDR_ADP_EVENT_MP-MAP_PROPERTY = WDY_UI_PROP_DEF-PROPERTY_NAME

0..N

0..N