SAP ABAP table /RPM/TS_TEMPLATE_D_DATA {SAP Field Configuration Item Template Data}


/RPM/TS_TEMPLATE_D_DATA-UNIT = /RPM/CAP_UNITS-UNIT
_RPM_CAP_UNITS
CLIENT [CLNT (3)]
UNIT [UNIT (3)]
/RPM/TS_TEMPLATE_D_DATA-CURRENCY = /RPM/CURRENCY-CURRENCY
_RPM_CURRENCY
CLIENT [CLNT (3)]
CURRENCY [CUKY (5)]
/RPM/TS_TEMPLATE_D_DATA-CAP_PERIODTYPE = /RPM/PERIOD_TYPE-PERIODTYPE
/RPM/TS_TEMPLATE_D_DATA-PERIODTYPE = /RPM/PERIOD_TYPE-PERIODTYPE
_RPM_PERIOD_TYPE
CLIENT [CLNT (3)]
PERIODTYPE [NUMC (2)]
_RPM_TS_TEMPLATE_D_DATA
CATEGORY [NUMC (4)]
SUBCATEGORY [NUMC (4)]
PTYPE [NUMC (4)]
TTYPE [NUMC (4)]
CURRENCY [CUKY (5)]
PERIODTYPE [NUMC (2)]
UNIT [UNIT (3)]
PRIORITY_GROUP [NUMC (2)]
CAP_PERIODTYPE [NUMC (2)]
LOCATION [CHAR (4)]
GEOGRAPHY [CHAR (4)]
/RPM/TS_TEMPLATE_D_DATA-GEOGRAPHY = DPR_AREA-AREA
DPR_AREA
MANDT [CLNT (3)]
AREA [CHAR (4)]
/RPM/TS_TEMPLATE_D_DATA-LOCATION = DPR_LOCATION-LOCATION
DPR_LOCATION
MANDT [CLNT (3)]
LOCATION [CHAR (4)]
/RPM/TS_TEMPLATE_D_DATA-CATEGORY = RPM_PROJ_CAT-CATEGORY
RPM_PROJ_CAT
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
/RPM/TS_TEMPLATE_D_DATA-PRIORITY_GROUP = RPM_PROJ_PRGRP-PRIORITY_GROUP
RPM_PROJ_PRGRP
MANDT [CLNT (3)]
PRIORITY_GROUP [NUMC (2)]
/RPM/TS_TEMPLATE_D_DATA-SUBCATEGORY = RPM_PROJ_SUBCAT-SUBCATEGORY
RPM_PROJ_SUBCAT
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
SUBCATEGORY [NUMC (4)]
/RPM/TS_TEMPLATE_D_DATA-TTYPE = RPM_PROJ_TTYPE-TTYPE
RPM_PROJ_TTYPE
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
TTYPE [NUMC (4)]
/RPM/TS_TEMPLATE_D_DATA-PTYPE = RPM_PROJ_TYPE-PTYPE
RPM_PROJ_TYPE
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
PTYPE [NUMC (4)]
0..N
1
1
1