SAP ABAP table ALM_ME_NOTIF_HEADER {Notification Header}

ALM_ME_NOTIF_HEADER

PLANPLANT [CHAR (4)]
EQUIPMENT [CHAR (18)]
ASSEMBLY [CHAR (18)]
UNIT [UNIT (3)]
PLANGROUP [CHAR (3)]
MNTPLAN [CHAR (12)]
MAINTITEM [CHAR (16)]
NOTIF_TYPE [CHAR (2)]
PRIOTYPE [CHAR (2)]
PRIORITY [CHAR (1)]
ORDERID [CHAR (12)]
MATERIAL [CHAR (18)]
CUST_NO [CHAR (10)]
OBJECT_NO [CHAR (22)]
CATPROFILE [CHAR (9)]
SALES_ORD [CHAR (10)]
DIVISION [CHAR (2)]
SALES_ORG [CHAR (4)]
DISTR_CHAN [CHAR (2)]
CAT_TYPE [CHAR (1)]
CODE_GROUP [CHAR (8)]
CODING [CHAR (4)]
PM_WKCTR [NUMC (8)]
SALES_OFFICE [CHAR (4)]
SALES_GRP [CHAR (3)]
NOTIFTMEZ [CHAR (6)]
FUNCT_LOC [CHAR (30)]
ABCINDIC [CHAR (1)]
MAINTPLANT [CHAR (4)]
MAINTLOC [CHAR (10)]
PLSECTN [CHAR (3)]
PP_WKCTR [NUMC (8)]
BUS_AREA [CHAR (4)]
CO_AREA [CHAR (4)]
COSTCENTER [CHAR (10)]
ASSET_NO [CHAR (12)]
SUB_NUMBER [CHAR (4)]
STDGORD [CHAR (12)]
STLMTORDER [CHAR (12)]
COMP_CODE [CHAR (4)]
SALES_ORG_LOC_ACC [CHAR (4)]
DIVISION_LOC_ACC [CHAR (2)]
DIST_CHAN_LOC_ACC [CHAR (2)]
DOC_NUMBER [CHAR (10)]
ITM_NUMBER [NUMC (6)]

ALM_ME_NOTIF_HEADER-SUB_NUMBER = ANLA-ANLN2 — 0..N

ANLA

MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]
ANLN2 [CHAR (4)]

ALM_ME_NOTIF_HEADER-ASSET_NO = ANLH-ANLN1 — 0..N

ANLH

MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

ALM_ME_NOTIF_HEADER-ORDERID = AUFK-AUFNR — 0..N

AUFK

MANDT [CLNT (3)]
AUFNR [CHAR (12)]

ALM_ME_NOTIF_HEADER-STDGORD = AUFK-AUFNR — 0..N

ALM_ME_NOTIF_HEADER-STLMTORDER = AUFK-AUFNR — 0..N

ALM_ME_NOTIF_HEADER-PM_WKCTR = CRID-OBJID — 0..N

CRID

MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

ALM_ME_NOTIF_HEADER-PP_WKCTR = CRID-OBJID — 0..N

ALM_ME_NOTIF_HEADER-COSTCENTER = CSKS-KOSTL — 0..N

CSKS

MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

ALM_ME_NOTIF_HEADER-EQUIPMENT = EQUI-EQUNR — 0..N

EQUI

MANDT [CLNT (3)]
EQUNR [CHAR (18)]

ALM_ME_NOTIF_HEADER-FUNCT_LOC = IFLOT-TPLNR — 0..N

IFLOT

MANDT [CLNT (3)]
TPLNR [CHAR (30)]

ALM_ME_NOTIF_HEADER-CUST_NO = KNA1-KUNNR — 0..N

KNA1

MANDT [CLNT (3)]
KUNNR [CHAR (10)]

ALM_ME_NOTIF_HEADER-ASSEMBLY = MARA-MATNR — 0..N

ALM_ME_NOTIF_HEADER-MATERIAL = MARA-MATNR — 0..N

MARA

MANDT [CLNT (3)]
MATNR [CHAR (18)]

ALM_ME_NOTIF_HEADER-MNTPLAN = MPLA-WARPL — 0..N

MPLA

MANDT [CLNT (3)]
WARPL [CHAR (12)]

ALM_ME_NOTIF_HEADER-MAINTITEM = MPOS-WAPOS — 0..N

MPOS

MANDT [CLNT (3)]
WAPOS [CHAR (16)]

ALM_ME_NOTIF_HEADER-OBJECT_NO = ONR00-OBJNR — 0..N

ONR00

MANDT [CLNT (3)]
OBJNR [CHAR (22)]

ALM_ME_NOTIF_HEADER-CODING = QPCD-CODE — 0..N

QPCD

MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]
CODE [CHAR (4)]

ALM_ME_NOTIF_HEADER-CODE_GROUP = QPGR-CODEGRUPPE — 0..N

QPGR

MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]

ALM_ME_NOTIF_HEADER-COMP_CODE = T001-BUKRS — 0..N

T001

MANDT [CLNT (3)]
BUKRS [CHAR (4)]

ALM_ME_NOTIF_HEADER-MAINTPLANT = T001W-WERKS — 0..N

T001W

MANDT [CLNT (3)]
WERKS [CHAR (4)]

ALM_ME_NOTIF_HEADER-UNIT = T006-MSEHI — 0..N

T006

MANDT [CLNT (3)]
MSEHI [UNIT (3)]

ALM_ME_NOTIF_HEADER-PLANGROUP = T024I-INGRP — 0..N

T024I

MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

ALM_ME_NOTIF_HEADER-CATPROFILE = T352B-RBNR — 0..N

T352B

MANDT [CLNT (3)]
RBNR [CHAR (9)]

ALM_ME_NOTIF_HEADER-PRIORITY = T356-PRIOK — 0..N

T356

MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

ALM_ME_NOTIF_HEADER-PRIOTYPE = T356A-ARTPR — 0..N

T356A

MANDT [CLNT (3)]
ARTPR [CHAR (2)]

ALM_ME_NOTIF_HEADER-PLSECTN = T357-BEBER — 0..N

T357

MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]

ALM_ME_NOTIF_HEADER-ABCINDIC = T370C-ABCKZ — 0..N

T370C

MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

ALM_ME_NOTIF_HEADER-PLANPLANT = T399I-IWERK — 0..N

T399I

MANDT [CLNT (3)]
IWERK [CHAR (4)]

ALM_ME_NOTIF_HEADER-MAINTLOC = T499S-STAND — 0..N

T499S

MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

ALM_ME_NOTIF_HEADER-BUS_AREA = TGSB-GSBER — 0..N

TGSB

MANDT [CLNT (3)]
GSBER [CHAR (4)]

ALM_ME_NOTIF_HEADER-CO_AREA = TKA01-KOKRS — 0..N

TKA01

MANDT [CLNT (3)]
KOKRS [CHAR (4)]

ALM_ME_NOTIF_HEADER-CAT_TYPE = TQ15-KATALOGART — 0..N

TQ15

MANDT [CLNT (3)]
KATALOGART [CHAR (2)]

ALM_ME_NOTIF_HEADER-NOTIF_TYPE = TQ80-QMART — 0..N

TQ80

MANDT [CLNT (3)]
QMART [CHAR (2)]

ALM_ME_NOTIF_HEADER-DIVISION = TSPA-SPART — 0..N

ALM_ME_NOTIF_HEADER-DIVISION_LOC_ACC = TSPA-SPART — 0..N

TSPA

MANDT [CLNT (3)]
SPART [CHAR (2)]

ALM_ME_NOTIF_HEADER-NOTIFTMEZ = TTZZ-TZONE — 0..N

TTZZ

CLIENT [CLNT (3)]
TZONE [CHAR (6)]

ALM_ME_NOTIF_HEADER-SALES_OFFICE = TVBUR-VKBUR — 0..N

TVBUR

MANDT [CLNT (3)]
VKBUR [CHAR (4)]

ALM_ME_NOTIF_HEADER-SALES_GRP = TVKGR-VKGRP — 0..N

TVKGR

MANDT [CLNT (3)]
VKGRP [CHAR (3)]

ALM_ME_NOTIF_HEADER-SALES_ORG = TVKO-VKORG — 0..N

TVKO

MANDT [CLNT (3)]
VKORG [CHAR (4)]

ALM_ME_NOTIF_HEADER-SALES_ORG_LOC_ACC = TVKO-VKORG — 0..N

ALM_ME_NOTIF_HEADER-DISTR_CHAN = TVTW-VTWEG — 0..N

TVTW

MANDT [CLNT (3)]
VTWEG [CHAR (2)]

ALM_ME_NOTIF_HEADER-DIST_CHAN_LOC_ACC = TVTW-VTWEG — 0..N

ALM_ME_NOTIF_HEADER-DOC_NUMBER = VBUK-VBELN — 0..N

VBUK

MANDT [CLNT (3)]
VBELN [CHAR (10)]

ALM_ME_NOTIF_HEADER-SALES_ORD = VBUK-VBELN — 0..N

VBUP

MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]

ALM_ME_NOTIF_HEADER-ITM_NUMBER = VBUP-POSNR — 0..N