SAP ABAP table COCB_MSD_S_COMH_IMSEG {Assignment of Process Message to Goods Movement Data}

COCB_MSD_S_COMH_IMSEG

MANDT [CLNT (3)]
WERK [CHAR (4)]
MSCLA [CHAR (8)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]
CHARG [CHAR (10)]
SOBKZ [CHAR (1)]
KUNNR [CHAR (10)]
BWTAR [CHAR (10)]
ERFME [UNIT (3)]
BPRME [UNIT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
UMMAT [CHAR (18)]
UMWRK [CHAR (4)]
UMLGO [CHAR (4)]
UMCHA [CHAR (10)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
LGPLA [CHAR (10)]
GRUND [NUMC (4)]
EVERS [CHAR (2)]
EVERE [CHAR (2)]
UMBAR [CHAR (10)]
MWSKZ [CHAR (2)]
TXJCD [CHAR (15)]
AUFNR [CHAR (12)]
PS_PSP_PNR [NUMC (8)]
KDAUF [CHAR (10)]
NPLNR [CHAR (12)]
WAERS [CUKY (5)]
VPTNR [CHAR (10)]
QPLOS [NUMC (12)]
BEMOT [CHAR (2)]

COCB_MSD_S_COMH_IMSEG-AUFNR = AUFK-AUFNR (0..N, 0..N)

AUFK

MANDT [CLNT (3)]
AUFNR [CHAR (12)]

COCB_MSD_S_COMH_IMSEG-NPLNR = AUFK-AUFNR (0..N, 0..N)

COCB_MSD_S_COMH_IMSEG-EBELN = EKKO-EBELN (0..N, 0..N)

EKKO

MANDT [CLNT (3)]
EBELN [CHAR (10)]

COCB_MSD_S_COMH_IMSEG-EBELP = EKPO-EBELP (0..N, 0..N)

EKPO

MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

COCB_MSD_S_COMH_IMSEG-KUNNR = KNA1-KUNNR (0..N, 0..N)

KNA1

MANDT [CLNT (3)]
KUNNR [CHAR (10)]

COCB_MSD_S_COMH_IMSEG-VPTNR = KNA1-KUNNR (0..N, 0..N)

LAGP

MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
LGPLA [CHAR (10)]

COCB_MSD_S_COMH_IMSEG-LGPLA = LAGP-LGPLA (0..N, 0..N)

COCB_MSD_S_COMH_IMSEG-MATNR = MARA-MATNR (0..N, 0..N)

MARA

MANDT [CLNT (3)]
MATNR [CHAR (18)]

COCB_MSD_S_COMH_IMSEG-UMMAT = MARA-MATNR (0..N, 0..N)

MCHA

MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
CHARG [CHAR (10)]

COCB_MSD_S_COMH_IMSEG-CHARG = MCHA-CHARG (0..N, 0..N)

COCB_MSD_S_COMH_IMSEG-UMCHA = MCHA-CHARG (0..N, 0..N)

PRPS

MANDT [CLNT (3)]
PSPNR [NUMC (8)]

COCB_MSD_S_COMH_IMSEG-PS_PSP_PNR = PRPS-PSPNR (0..N, 0..N)

QALS

MANDANT [CLNT (3)]
PRUEFLOS [NUMC (12)]

COCB_MSD_S_COMH_IMSEG-QPLOS = QALS-PRUEFLOS (0..N, 0..N)

T000

MANDT [CLNT (3)]

COCB_MSD_S_COMH_IMSEG-MANDT = T000-MANDT (0..N, 0..N)

T001L

MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

COCB_MSD_S_COMH_IMSEG-LGORT = T001L-LGORT (1, 0..N)

COCB_MSD_S_COMH_IMSEG-UMLGO = T001L-LGORT (0..N, 0..N)

T001W

MANDT [CLNT (3)]
WERKS [CHAR (4)]

COCB_MSD_S_COMH_IMSEG-UMWRK = T001W-WERKS (0..N, 0..N)

COCB_MSD_S_COMH_IMSEG-WERK = T001W-WERKS (0..N, 0..N)

COCB_MSD_S_COMH_IMSEG-WERKS = T001W-WERKS (1, 0..N)

T006

MANDT [CLNT (3)]
MSEHI [UNIT (3)]

COCB_MSD_S_COMH_IMSEG-BPRME = T006-MSEHI (0..N, 0..N)

COCB_MSD_S_COMH_IMSEG-ERFME = T006-MSEHI (0..N, 0..N)

T007A

MANDT [CLNT (3)]
KALSM [CHAR (6)]
MWSKZ [CHAR (2)]

COCB_MSD_S_COMH_IMSEG-MWSKZ = T007A-MWSKZ (0..N, 0..N)

T027A

MANDT [CLNT (3)]
EVERS [CHAR (2)]

COCB_MSD_S_COMH_IMSEG-EVERS = T027A-EVERS (0..N, 0..N)

T027C

MANDT [CLNT (3)]
EVERS [CHAR (2)]
EVERE [CHAR (2)]

COCB_MSD_S_COMH_IMSEG-EVERE = T027C-EVERE (0..N, 0..N)

T148

MANDT [CLNT (3)]
SOBKZ [CHAR (1)]

COCB_MSD_S_COMH_IMSEG-SOBKZ = T148-SOBKZ (0..N, 0..N)

T149D

MANDT [CLNT (3)]
BWTAR [CHAR (10)]

COCB_MSD_S_COMH_IMSEG-BWTAR = T149D-BWTAR (0..N, 0..N)

COCB_MSD_S_COMH_IMSEG-UMBAR = T149D-BWTAR (0..N, 0..N)

T157D

MANDT [CLNT (3)]
BWART [CHAR (3)]
GRUND [NUMC (4)]

COCB_MSD_S_COMH_IMSEG-GRUND = T157D-GRUND (0..N, 0..N)

T300

MANDT [CLNT (3)]
LGNUM [CHAR (3)]

COCB_MSD_S_COMH_IMSEG-LGNUM = T300-LGNUM (0..N, 0..N)

T301

MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]

COCB_MSD_S_COMH_IMSEG-LGTYP = T301-LGTYP (0..N, 0..N)

TBMOT

MANDT [CLNT (3)]
BEMOT [CHAR (2)]

COCB_MSD_S_COMH_IMSEG-BEMOT = TBMOT-BEMOT (0..N, 0..N)

TC50

MANDT [CLNT (3)]
WERKS [CHAR (4)]
CSTYP [CHAR (2)]
COSTR [CHAR (8)]

COCB_MSD_S_COMH_IMSEG-MSCLA = TC50-COSTR (0..N, 0..N)

TCURC

MANDT [CLNT (3)]
WAERS [CUKY (5)]

COCB_MSD_S_COMH_IMSEG-WAERS = TCURC-WAERS (0..N, 0..N)

TTXJ

MANDT [CLNT (3)]
KALSM [CHAR (6)]
TXJCD [CHAR (15)]

COCB_MSD_S_COMH_IMSEG-TXJCD = TTXJ-TXJCD (0..N, 0..N)

VBUK

MANDT [CLNT (3)]
VBELN [CHAR (10)]

COCB_MSD_S_COMH_IMSEG-KDAUF = VBUK-VBELN (0..N, 0..N)