SAP ABAP table CYAUPM {Generated Table for View}


CYAUPM
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
PLNBEZ [CHAR (18)]
GMEIN [UNIT (3)]
PLNAW [CHAR (1)]
PVERW [CHAR (3)]
PLGRP [CHAR (3)]
DISPO [CHAR (3)]
FEVOR [CHAR (3)]
AUART [CHAR (4)]
BUKRS [CHAR (4)]
WERKS [CHAR (4)]
GSBER [CHAR (4)]
KOKRS [CHAR (4)]
KOSTV [CHAR (10)]
ABKRS [NUMC (2)]
KSTAR [CHAR (10)]
KOSTL [CHAR (10)]
SAKNR [CHAR (10)]
OBJNR [CHAR (22)]
PRONR [NUMC (8)]
EQUNR [CHAR (18)]
BAUTL [CHAR (18)]
ILOAN [CHAR (12)]
ANLZU [CHAR (1)]
IWERK [CHAR (4)]
INGPR [CHAR (3)]
APGRP [CHAR (3)]
WARPL [CHAR (12)]
REVNR [CHAR (8)]
TPLNR [CHAR (30)]
SWERK [CHAR (4)]
STORT [CHAR (10)]
BEBER [CHAR (3)]
ILART [CHAR (3)]
PSPEL [NUMC (8)]
CYAUPM-AUFNR = AUFK-AUFNR
AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
CYAUPM-KSTAR = CSKB-KSTAR
CSKB
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KSTAR [CHAR (10)]
DATBI [DATS (8)]
CYAUPM-KOSTL = CSKS-KOSTL
CYAUPM-KOSTV = CSKS-KOSTL
CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]
CYAUPM-EQUNR = EQUI-EQUNR
EQUI
MANDT [CLNT (3)]
EQUNR [CHAR (18)]
CYAUPM-TPLNR = IFLOT-TPLNR
IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]
CYAUPM-ILOAN = ILOA-ILOAN
ILOA
MANDT [CLNT (3)]
ILOAN [CHAR (12)]
CYAUPM-BAUTL = MARA-MATNR
CYAUPM-PLNBEZ = MARA-MATNR
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
CYAUPM-WARPL = MPLA-WARPL
MPLA
MANDT [CLNT (3)]
WARPL [CHAR (12)]
CYAUPM-OBJNR = ONR00-OBJNR
ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]
CYAUPM-PRONR = PROJ-PSPNR
PROJ
MANDT [CLNT (3)]
PSPNR [NUMC (8)]
CYAUPM-PSPEL = PRPS-PSPNR
PRPS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]
CYAUPM-SAKNR = SKB1-SAKNR
SKB1
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SAKNR [CHAR (10)]
CYAUPM-MANDT = T000-MANDT
T000
MANDT [CLNT (3)]
CYAUPM-BUKRS = T001-BUKRS
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
CYAUPM-SWERK = T001W-WERKS
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
CYAUPM-WERKS = T001W-WERKS
CYAUPM-AUART = T003O-AUART
CYAUPM-GMEIN = T006-MSEHI
T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]
CYAUPM-APGRP = T024A-FEVOR
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
CYAUPM-PLGRP = T024A-FEVOR
T024A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]
CYAUPM-DISPO = T024D-DISPO
T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]
CYAUPM-FEVOR = T024F-FEVOR
T024F
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]
CYAUPM-INGPR = T024I-INGRP
T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]
CYAUPM-REVNR = T352R-REVNR
T352R
MANDT [CLNT (3)]
IWERK [CHAR (4)]
REVNR [CHAR (8)]
CYAUPM-ILART = T353I-ILART
T353I
MANDT [CLNT (3)]
ILART [CHAR (3)]
CYAUPM-BEBER = T357-BEBER
T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (3)]
CYAUPM-ANLZU = T357M-ANLZU
T357M
MANDT [CLNT (3)]
ANLZU [CHAR (1)]
CYAUPM-IWERK = T399I-IWERK
T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
CYAUPM-PVERW = T411-VERWE
T411
MANDT [CLNT (3)]
VERWE [CHAR (3)]
CYAUPM-STORT = T499S-STAND
T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]
CYAUPM-PLNAW = TCA09-PLNAW
TCA09
MANDT [CLNT (3)]
PLNAW [CHAR (1)]
CYAUPM-GSBER = TGSB-GSBER
TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]
CYAUPM-KOKRS = TKA01-KOKRS
TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
CYAUPM-ABKRS = TKO08-ABKRS
TKO08
CLIENT [CLNT (3)]
KOKRS [CHAR (4)]
ABKRS [NUMC (2)]
1
0..N
{0,1}
{0,1}
{0,1}