SAP ABAP table DIQMELX {PM Notification}

DIQMELX-/SAPSMOSS/ADDID = /SAPSMOSS/ADDID-R3ADDID

/SAPSMOSS/ADDID
MANDT [CLNT (3)]
R3ADDID [CHAR (100)]

DIQMELX-/SAPSMOSS/ADDREL = /SAPSMOSS/ADDREL-R3ADDREL

/SAPSMOSS/ADDREL
MANDT [CLNT (3)]
R3ADDREL [CHAR (100)]

DIQMELX-/SAPSMOSS/DBSYS = /SAPSMOSS/DBSYS-DBSYS

/SAPSMOSS/DBSY
MANDT [CLNT (3)]
DBSYS [CHAR (10)]

DIQMELX-/SAPSMOSS/FRONT = /SAPSMOSS/FRNT-FRONTEND

/SAPSMOSS/FRNT
MANDT [CLNT (3)]
FRONTEND [CHAR (100)]

DIQMELX-/SAPSMOSS/INSTN = /SAPSMOSS/INSTN-R3INSTN

/SAPSMOSS/INSTN
MANDT [CLNT (3)]
R3INSTN [CHAR (100)]

DIQMELX-/SAPSMOSS/OSSYS = /SAPSMOSS/OSSYS-OSSYS

/SAPSMOSS/OSYS
MANDT [CLNT (3)]
OSSYS [CHAR (100)]

DIQMELX-/SAPSMOSS/REL = /SAPSMOSS/REL-R3REL

/SAPSMOSS/REL
MANDT [CLNT (3)]
R3REL [CHAR (100)]

DIQMELX-/SAPSMOSS/STATUS = /SAPSMOSS/STAT-STATUS

/SAPSMOSS/STAT
STATUS [CHAR (1)]

DIQMELX-/SAPSMOSS/SYSTYP = /SAPSMOSS/SYST-R3SYSTYP

/SAPSMOSS/SYST
MANDT [CLNT (3)]
R3SYSTYP [CHAR (11)]

DIQMELX-ANLUN = ANLA-ANLN2

ANLA
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN2 [CHAR (12)]
ANLN2 [CHAR (4)]

DIQMELX-ANLNR = ANLH-ANLN1

ANLH
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
ANLN1 [CHAR (12)]

DIQMELX-AUFNR = AUFK-AUFNR

AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

DIQMELX-OAUFNR = AUFK-AUFNR

DIQMELX-DAUFN = AUFK-AUFNR

DIQMELX-FERTAUFNR = AUFK-AUFNR

CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]

DIQMELX-KAUFN = AUFK-AUFNR

DIQMELX-ARBPL = CRID-OBJID

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

DIQMELX-PPSID = CRID-OBJID

DIQMELX-KOSTL = CSKS-KOSTL

DIQMELX-EBELN = EKKO-EBELN

EKKO
MANDT [CLNT (3)]
EBELN [CHAR (10)]

DIQMELX-EBELP = EKPO-EBELP

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

DIQMELX-BEQUI = EQUI-EQUNR

EQUI
MANDT [CLNT (3)]
EQUNR [CHAR (18)]

DIQMELX-EQUNR = EQUI-EQUNR

IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]

DIQMELX-BTPLN = IFLOT-TPLNR

DIQMELX-TPLNR = IFLOT-TPLNR

ILOA
MANDT [CLNT (3)]
ILOAN [CHAR (12)]

DIQMELX-ILOAN = ILOA-ILOAN

DIQMELX-KUNUM = KNA1-KUNNR

KNA1
MANDT [CLNT (3)]
KUNNR [CHAR (10)]

DIQMELX-HERSTELLER = LFA1-LIFNR

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

DIQMELX-LIFNUM = LFA1-LIFNR

DIQMELX-BAUTL = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

DIQMELX-EMATNR = MARA-MATNR

MCH1
MANDT [CLNT (3)]
MATNR [CHAR (18)]
CHARG [CHAR (10)]

DIQMELX-MATNR = MARA-MATNR

DIQMELX-CHARG = MCH1-CHARG

MKAL
MANDT [CLNT (3)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
VERID [CHAR (4)]

DIQMELX-RM_MATNR = MKAL-MATNR

DIQMELX-RM_WERKS = MKAL-WERKS

DIQMELX-VERID = MKAL-VERID

MPLA
MANDT [CLNT (3)]
WARPL [CHAR (12)]

DIQMELX-WARPL = MPLA-WARPL

ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]

DIQMELX-OBJNR = ONR00-OBJNR

DIQMELX-OBJNR_REAL = ONR00-OBJNR

DIQMELX-OBJNR_STAT = ONR00-OBJNR

QALS
MANDT [CLNT (3)]
PRUEFLOS [NUMC (12)]

DIQMELX-PRUEFLOS = QALS-PRUEFLOS

QHEL
MANDT [CLNT (3)]
QMNUM [CHAR (12)]

DIQMELX-QMNUM = QHEL-QMNUM

DIQMELX-QWNUM = QHEL-QMNUM

QPGR
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]
CODEGRUPPE [CHAR (8)]

DIQMELX-QMGRP = QPGR-CODEGRUPPE

SAFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]

DIQMELX-SA_AUFNR = SAFK-AUFNR

T000
MANDT [CLNT (3)]

DIQMELX-MANDT = T000-MANDT

T001
MANDT [CHAR (3)]
BUKRS [CHAR (4)]

DIQMELX-BUKRS = T001-BUKRS

T001L
MANDT [CHAR (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]

DIQMELX-LGORTCHARG = T001L-LGORT

DIQMELX-LGORTVORG = T001L-LGORT

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

DIQMELX-ARBPLWERK = T001W-WERKS

DIQMELX-MAWERK = T001W-WERKS

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

DIQMELX-SWERK = T001W-WERKS

DIQMELX-MAUEH = T006-MSEHI

T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]

DIQMELX-MGEIN = T006-MSEHI

T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]

DIQMELX-MATKL = T023-MATKL

T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]

DIQMELX-BKGRP = T024-EKGRP

T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]

DIQMELX-EKORG = T024E-EKORG

T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]

DIQMELX-INGRP = T024I-INGRP

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

DIQMELX-PRDHA = T179-PRODH

T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]

DIQMELX-RBNR = T352B-RBNR

T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]

DIQMELX-PRIOK = T356-PRIOK

T357
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BEBER [CHAR (1)]

DIQMELX-ARTPR = T356A-ARTPR

T357A
MANDT [CLNT (3)]
AUSWK [CHAR (11)]

DIQMELX-BEBER = T357-BEBER

T357Z
MANDT [CLNT (3)]
ANLAZ [CHAR (1)]

DIQMELX-AUSWK = T357A-AUSWK

T370C
MANDT [CLNT (3)]
ABCKZ [CHAR (1)]

DIQMELX-ANLZR = T357Z-ANLAZ

T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]

DIQMELX-ANLZN = T357Z-ANLAZ

DIQMELX-ANLZV = T357Z-ANLAZ

DIQMELX-ABCKZ = T370C-ABCKZ

T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]

DIQMELX-IWERK = T399I-IWERK

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

DIQMELX-STORT = T499S-STAND

TG5B
MANDT [CLNT (3)]
GSBER [CHAR (4)]

DIQMELX-WAERS = TCURC-WAERS

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

DIQMELX-GSBER = TG5B-GSBER

TO15
MANDT [CLNT (3)]
KATALOGART [CHAR (2)]

DIQMELX-KOKRS = TKA01-KOKRS

TQ80
MANDT [CLNT (3)]
QMART [CHAR (2)]

DIQMELX-KATALOGART = TO15-KATALOGART

TQ81
MANDT [CLNT (3)]
AUSWRK [CHAR (4)]

DIQMELX-QMART = TQ80-QMART

TQ81V
MANDT [CLNT (3)]
TEILEV [CHAR (4)]

DIQMELX-AUSWRK = TQ81-AUSWRK

TQ86
MANDT [CLNT (3)]
FEART [CHAR (8)]

DIQMELX-TEILEV = TQ81V-TEILEV

TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]

DIQMELX-FEART = TQ86-FEART

TTSEGTPLH
CLIENT [CLNT (3)]
TEPL [CHAR (18)]

DIQMELX-SPART = TSPA-SPART

TTZZ
CLIENT [CLNT (3)]
TZONE [CHAR (6)]

DIQMELX-TSEGTP = TTSEGTPLH-TEPL

TVBVK
MANDT [CLNT (3)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]

DIQMELX-TZONO = TTZZ-TZONE

TVKBZ
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
SPART [CHAR (2)]
VKBUR [CHAR (4)]

DIQMELX-VKGRP = TVBVK-VKGRP

TVKO
MANDT [CLNT (3)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]

DIQMELX-VKBUR = TVKBZ-VKBUR

TVTW
MANDT [CLNT (3)]
VTWEG [CHAR (2)]

DIQMELX-VKORG = TVKO-VKORG

VBUK
MANDT [CLNT (3)]
VBELN [CHAR (10)]

DIQMELX-VTWEG = TVTW-VTWEG

VBUP
MANDT [CLNT (3)]
VBELN [CHAR (10)]
POSNR [NUMC (6)]

DIQMELX-KDAUF = VBUK-VBELN

DIQMELX-LS_KDAUF = VBUK-VBELN

DIQMELX-LS_VBELN = VBUK-VBELN

DIQMELX-VBELN = VBUK-VBELN

DIQMELX-KDPOS = VBUP-POSNR

DIQMELX-LS_KDPOS = VBUP-POSNR

DIQMELX-LS_POSNR = VBUP-POSNR

DIQMELX {PM Notification}
MANDT [CLNT (3)]
QMNUM [CHAR (12)]
QMART [CHAR (2)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]
ANLKR [CHAR (2)]
AUFNR [CHAR (12)]
VERID [CHAR (4)]
RM_MATNR [CHAR (18)]
RM_WERKS [CHAR (4)]
SA_AUFNR [CHAR (12)]
MATNR [CHAR (18)]
MATKL [CHAR (9)]
PNDNA [CHAR (18)]
AUNUM [CHAR (10)]
OBJNR [CHAR (22)]
SPART [CHAR (2)]
VKORG [CHAR (4)]
VTWEG [CHAR (2)]
MAWERK [CHAR (4)]
QMKAT [CHAR (1)]
QMGRP [CHAR (8)]
AUSWWK [CHAR (4)]
TEILEV [CHAR (4)]
PRUEFLOS [NUMC (12)]
CHARG [CHAR (10)]
LGORTCHARG [CHAR (4)]
HERSTELLER [CHAR (10)]
EMATNR [CHAR (18)]
ERDRG [CHAR (4)]
BKGRP [CHAR (3)]
LGORTVORG [CHAR (4)]
FERTAUFNR [CHAR (12)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]
LS_KDAUF [CHAR (10)]
LS_KDPOS [NUMC (6)]
LS_VBELN [CHAR (10)]
LS_POSNR [NUMC (6)]
ARBPL [NUMC (8)]
ARBPLWERK [CHAR (4)]
FEART [CHAR (8)]
MEGIN [UNIT (3)]
CODAFNR [CHAR (12)]
QWRNUM [CHAR (12)]
VKBUR [CHAR (4)]
VKGRP [CHAR (3)]
TSEGTP [CHAR (10)]
TZONO [CHAR (6)]
_SAPSMOSS_MSTN [CHAR (10)]
_SAPSMOSS_OSSYS [CHAR (100)]
_SAPSMOSS_DBSYS [CHAR (10)]
_SAPSMOSS_REL [CHAR (100)]
_SAPSMOSS_FRONT [CHAR (100)]
_SAPSMOSS_SYSTYP [CHAR (11)]
_SAPSMOSS_ADDID [CHAR (100)]
_SAPSMOSS_ADDREL [CHAR (100)]
_SAPSMOSS_STATUS [CHAR (1)]
OBJNR_REAL [CHAR (22)]
OBJNR_STAT [CHAR (22)]
IWERK [CHAR (4)]
ILOAN [CHAR (12)]
ZGUNR [CHAR (18)]
BKUTL [CHAR (18)]
MAUEH [UNIT (3)]
RTPLN [CHAR (50)]
BEQUI [CHAR (18)]
AUSWK [CHAR (11)]
ANLZV [CHAR (1)]
ANLZN [CHAR (1)]
ANLZR [CHAR (1)]
INGRP [CHAR (3)]
TRAR [CHAR (50)]
ABCKZ [CHAR (1)]
SWERK [CHAR (4)]
STORT [CHAR (10)]
BEBER [CHAR (1)]
PPSID [NUMC (8)]
GSBER [CHAR (4)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
BUKRS [CHAR (4)]
ANLNR [CHAR (12)]
ANLUN [CHAR (4)]
DAUFN [CHAR (12)]
KAUFN [CHAR (12)]
KDAUF [CHAR (10)]
KDPOS [NUMC (6)]
ABRPL [CHAR (2)]