SAP ABAP table ENT2280 {Generated Table for View}


ENT2280
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
BELNR [CHAR (10)]
GJAHR [NUMC (4)]
BUZEI [NUMC (3)]
BSCHL [CHAR (2)]
UMSKZ [CHAR (1)]
GSBER [CHAR (4)]
PARGB [CHAR (4)]
MWSKZ [CHAR (2)]
PSWSL [CUKY (5)]
VBUND [CHAR (6)]
BEWAR [CHAR (3)]
HKONT [CHAR (10)]
WERKS [CHAR (4)]
MEINS [UNIT (3)]
BWKEY [CHAR (4)]
BWTAR [CHAR (10)]
SKB1
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
SAKNR [CHAR (10)]
T000
MANDT [CLNT (3)]
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
T001K
MANDT [CLNT (3)]
BWKEY [CHAR (4)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T007A
MANDT [CLNT (3)]
KALSM [CHAR (6)]
MWSKZ [CHAR (2)]
T074U
MANDT [CLNT (3)]
KOART [CHAR (1)]
UMSKZ [CHAR (1)]
T149D
MANDT [CLNT (3)]
BWTAR [CHAR (10)]
T856
MANDT [CLNT (3)]
TRTYP [CHAR (3)]
T880
MANDT [CLNT (3)]
RCOMP [CHAR (6)]
TBSL
MANDT [CLNT (3)]
BSCHL [CHAR (2)]
TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]
TGSB
MANDT [CLNT (3)]
GSBER [CHAR (4)]
ENT2280-HKONT = SKB1-SAKNR
ENT2280-MANDT = T000-MANDT
ENT2280-BUKRS = T001-BUKRS
ENT2280-BWKEY = T001K-BWKEY
ENT2280-WERKS = T001W-WERKS
ENT2280-MEINS = T006-MSEHI
ENT2280-MWSKZ = T007A-MWSKZ
ENT2280-UMSKZ = T074U-UMSKZ
ENT2280-BWTAR = T149D-BWTAR
ENT2280-BEWAR = T856-TRTYP
ENT2280-VBUND = T880-RCOMP
ENT2280-BSCHL = TBSL-BSCHL
ENT2280-PSWSL = TCURC-WAERS
ENT2280-GSBER = TGSB-GSBER
ENT2280-PARGB = TGSB-GSBER
0..N
1 1 1{0,1}
{0,1}
{0,1}