SAP ABAP table ENT5392 {Generated Table for View}


ENT5392
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
TANUM [NUMC (10)]
TAPOS [NUMC (4)]
MATNR [CHAR (18)]
WERKS [CHAR (4)]
SOBKZ [CHAR (1)]
MEINS [UNIT (3)]
ALTME [UNIT (3)]
LETYP [CHAR (3)]
LDEST [CHAR (4)]
VLTYP [CHAR (3)]
VLBER [CHAR (3)]
NLTYP [CHAR (3)]
NLBER [CHAR (3)]
RLTYP [CHAR (3)]
RLBER [CHAR (3)]
KZDIF [CHAR (1)]
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
T148
MANDT [CLNT (3)]
SOBKZ [CHAR (1)]
T300
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
T301
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
T302
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
LGBER [CHAR (3)]
T307
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LETYP [CHAR (3)]
T336
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
KZDIF [CHAR (1)]
TSP03
PADEST [CHAR (4)]
ENT5392-MATNR = MARA-MATNR
ENT5392-WERKS = T001W-WERKS
ENT5392-ALTME = T006-MSEHI
ENT5392-MEINS = T006-MSEHI
ENT5392-SOBKZ = T148-SOBKZ
ENT5392-LGNUM = T300-LGNUM
ENT5392-NLTYP = T301-LGTYP
ENT5392-RLTYP = T301-LGTYP
ENT5392-VLTYP = T301-LGTYP
ENT5392-NLBER = T302-LGBER
ENT5392-RLBER = T302-LGBER
ENT5392-VLBER = T302-LGBER
ENT5392-LETYP = T307-LETYP
ENT5392-KZDIF = T336-KZDIF
ENT5392-LDEST = TSP03-PADEST
1,1
{0,1}
1
1
0..N
0..N
0..N