SAP ABAP table MSAM10_NOTIF_HEADER {Notification Header}

MSAM10_NOTIF_HEADER
- *PLANPLANT* [CHAR (4)]
- *EQUIPMENT* [CHAR (18)]
- *ASSEMBLY* [CHAR (18)]
- *PLANGROUP* [CHAR (3)]
- *MNTPLAN* [CHAR (12)]
- *MAINTITEM* [CHAR (16)]
- *NOTIF_TYPE* [CHAR (2)]
- *PRIOTYPE* [CHAR (2)]
- *PRIORITY* [CHAR (1)]
- *ORDERID* [CHAR (12)]
- *MATERIAL* [CHAR (18)]
- *CUST_NO* [CHAR (10)]
- *OBJECT_NO* [CHAR (22)]
- *CATPROFILE* [CHAR (9)]
- *SALES_ORD* [CHAR (10)]
- *DIVISION* [CHAR (2)]
- *SALES_ORG* [CHAR (4)]
- *DISTR_CHAN* [CHAR (2)]
- *CAT_TYPE* [CHAR (1)]
- *CODE_GROUP* [CHAR (8)]
- *CODING* [CHAR (4)]
- *PM_WKCTR* [NUMC (8)]
- *FUNCT_LOC* [CHAR (30)]
- *MAINTPLANT* [CHAR (4)]
- *MAINTLOC* [CHAR (10)]
- *ASSET_NO* [CHAR (12)]
- *SUB_NUMBER* [CHAR (4)]
- *COMP_CODE* [CHAR (4)]
- *DOC_NUMBER* [CHAR (10)]
- *ITM_NUMBER* [NUMC (6)]

MSAM10_NOTIF_HEADER-SUB_NUMBER = ANLA-ANLN2 — 0..N

ANLA
- MANDT [CLNT (3)]
- *BUKRS* [CHAR (4)]
- *ANLN1* [CHAR (12)]
- ANLN2 [CHAR (4)]

MSAM10_NOTIF_HEADER-ASSET_NO = ANLH-ANLN1 — 0..N

ANLH
- MANDT [CLNT (3)]
- *BUKRS* [CHAR (4)]
- ANLN1 [CHAR (12)]

MSAM10_NOTIF_HEADER-ORDERID = AUFK-AUFNR — 0..N

AUFK
- *MANDT* [CLNT (3)]
- AUFNR [CHAR (12)]

MSAM10_NOTIF_HEADER-PM_WKCTR = CRID-OBJID — 0..N

CRID
- *MANDT* [CLNT (3)]
- OBJTY [CHAR (2)]
- OBJID [NUMC (8)]

MSAM10_NOTIF_HEADER-EQUIPMENT = EQUI-EQUNR — 0..N

EQUI
- *MANDT* [CLNT (3)]
- EQUNR [CHAR (18)]

MSAM10_NOTIF_HEADER-FUNCT_LOC = IFLOT-TPLNR — 0..N

IFLOT
- *MANDT* [CLNT (3)]
- TPLNR [CHAR (30)]

MSAM10_NOTIF_HEADER-CUST_NO = KNA1-KUNNR — 0..N

KNA1
- *MANDT* [CLNT (3)]
- KUNNR [CHAR (10)]

MSAM10_NOTIF_HEADER-ASSEMBLY = MARA-MATNR — 0..N

MARA
- *MANDT* [CLNT (3)]
- MATNR [CHAR (18)]

MSAM10_NOTIF_HEADER-MATERIAL = MARA-MATNR — 0..N

MSAM10_NOTIF_HEADER-MNTPLAN = MPLA-WARPL — 0..N

MPLA
- *MANDT* [CLNT (3)]
- WARPL [CHAR (12)]

MSAM10_NOTIF_HEADER-MAINTITEM = MPOS-WAPOS — 0..N

MPOS
- *MANDT* [CLNT (3)]
- WAPOS [CHAR (16)]

MSAM10_NOTIF_HEADER-OBJECT_NO = ONR00-OBJNR — 0..N

ONR00
- *MANDT* [CLNT (3)]
- OBJNR [CHAR (22)]

MSAM10_NOTIF_HEADER-CODING = QPCD-CODE — 0..N

QPCD
- *MANDT* [CLNT (3)]
- *KATALOGART* [CHAR (2)]
- *CODEGRUPPE* [CHAR (8)]
- CODE [CHAR (4)]

MSAM10_NOTIF_HEADER-CODE_GROUP = QPGR-CODEGRUPPE — 0..N

QPGR
- *MANDT* [CLNT (3)]
- *KATALOGART* [CHAR (2)]
- CODEGRUPPE [CHAR (8)]

MSAM10_NOTIF_HEADER-COMP_CODE = T001-BUKRS — 0..N

T001
- *MANDT* [CLNT (3)]
- BUKRS [CHAR (4)]

MSAM10_NOTIF_HEADER-MAINTPLANT = T001W-WERKS — 0..N

T001W
- *MANDT* [CLNT (3)]
- WERKS [CHAR (4)]

MSAM10_NOTIF_HEADER-PLANGROUP = T024I-INGRP — 0..N

T024I
- *MANDT* [CLNT (3)]
- *IWERK* [CHAR (4)]
- INGRP [CHAR (3)]

MSAM10_NOTIF_HEADER-CATPROFILE = T352B-RBNR — 0..N

T352B
- *MANDT* [CLNT (3)]
- RBNR [CHAR (9)]

MSAM10_NOTIF_HEADER-PRIORITY = T356-PRIOK — 0..N

T356
- *MANDT* [CLNT (3)]
- *ARTPR* [CHAR (2)]
- PRIOK [CHAR (1)]

MSAM10_NOTIF_HEADER-PRIOTYPE = T356A-ARTPR — 0..N

T356A
- *MANDT* [CLNT (3)]
- ARTPR [CHAR (2)]

MSAM10_NOTIF_HEADER-PLANPLANT = T399I-IWERK — 0..N

T399I
- *MANDT* [CLNT (3)]
- *IWERK* [CHAR (4)]

MSAM10_NOTIF_HEADER-MAINTLOC = T499S-STAND — 0..N

T499S
- *MANDT* [CLNT (3)]
- *WERKS* [CHAR (4)]
- STAND [CHAR (10)]

MSAM10_NOTIF_HEADER-CAT_TYPE = TQ15-KATALOGART — 0..N

TQ15
- MANDT [CLNT (3)]
- KATALOGART [CHAR (2)]

MSAM10_NOTIF_HEADER-NOTIF_TYPE = TQ80-QMART — 0..N

TQ80
- *MANDT* [CLNT (3)]
- QMART [CHAR (2)]

MSAM10_NOTIF_HEADER-DIVISION = TSPA-SPART — 0..N

TSPA
- MANDT [CLNT (3)]
- SPART [CHAR (2)]

MSAM10_NOTIF_HEADER-SALES_ORG = TVKO-VKORG — 0..N

TVKO
- MANDT [CLNT (3)]
- VKORG [CHAR (4)]

MSAM10_NOTIF_HEADER-DISTR_CHAN = TVTW-VTWEG — 0..N

TVTW
- MANDT [CLNT (3)]
- VTWEG [CHAR (2)]

MSAM10_NOTIF_HEADER-DOC_NUMBER = VBUK-VBELN — 0..N

MSAM10_NOTIF_HEADER-SALES_ORD = VBUK-VBELN — 0..N

VBUK
- *MANDT* [CLNT (3)]
- VBELN [CHAR (10)]

MSAM10_NOTIF_HEADER-ITM_NUMBER = VBUP-POSNR — 0..N

VBUP
- *MANDT* [CLNT (3)]
- *VBELN* [CHAR (10)]
- POSNR [NUMC (6)]