SAP ABAP table RIHAUFKU {Sub-orders (only for download)}

RIHAUFKU
- *AUFNR* [CHAR (12)]
- *AUART* [CHAR (4)]
- *WAERS* [CUKY (5)]
- *BUKRS* [CHAR (4)]
- *WERKS* [CHAR (4)]
- *GSBER* [CHAR (4)]
- *KOKRS* [CHAR (4)]
- *KOSTV* [CHAR (10)]
- *ABCKZ* [CHAR (1)]
- *EQUNR* [CHAR (18)]
- *BAUTL* [CHAR (18)]
- *ANLZU* [CHAR (1)]
- *IWERK* [CHAR (4)]
- *INGPR* [CHAR (3)]
- *APGRP* [CHAR (3)]
- *AWERK* [CHAR (4)]
- *KUNUM* [CHAR (10)]
- *KOSTL* [CHAR (10)]
- *SWERK* [CHAR (4)]
- *STORT* [CHAR (10)]
- *BEBER* [CHAR (3)]
- *TPLNR* [CHAR (30)]
- *ANLNR* [CHAR (12)]
- *ANLUN* [CHAR (4)]
- *REVNR* [CHAR (8)]
- *WARPL* [CHAR (12)]
- *FEVOR* [CHAR (3)]
- *ILART* [CHAR (3)]
- *QMNUM* [CHAR (12)]
- *MANDT* [CLNT (3)]
- *OBJNR* [CHAR (22)]
- *KDAUF* [CHAR (10)]
- *KDPOS* [NUMC (6)]
- *LEAD_AUFNR* [CHAR (12)]
- *MAUFNR* [CHAR (12)]

ANLA
- MANDT [CLNT (3)]
- *BUKRS* [CHAR (4)]
- *ANLN1* [CHAR (12)]
- ANLN2 [CHAR (4)]

ANLH
- MANDT [CLNT (3)]
- *BUKRS* [CHAR (4)]
- ANLN1 [CHAR (12)]

AUFK
- *MANDT* [CLNT (3)]
- AUFNR [CHAR (12)]

CSKS
- MANDT [CLNT (3)]
- *KOKRS* [CHAR (4)]
- KOSTL [CHAR (10)]
- DATBI [DATS (8)]

EQUI
- *MANDT* [CLNT (3)]
- EQUNR [CHAR (18)]

IFLOT
- *MANDT* [CLNT (3)]
- TPLNR [CHAR (30)]

KNA1
- *MANDT* [CLNT (3)]
- KUNNR [CHAR (10)]

MARA
- *MANDT* [CLNT (3)]
- MATNR [CHAR (18)]

MPLA
- *MANDT* [CLNT (3)]
- WARPL [CHAR (12)]

ONR00
- *MANDT* [CLNT (3)]
- OBJNR [CHAR (22)]

QMEL
- *MANDT* [CLNT (3)]
- QMNUM [CHAR (12)]

T000
- MANDT [CLNT (3)]

T001
- *MANDT* [CLNT (3)]
- BUKRS [CHAR (4)]

T001W
- *MANDT* [CLNT (3)]
- WERKS [CHAR (4)]

T003O
- *CLIENT* [CLNT (3)]
- AUART [CHAR (4)]

T024A
- *MANDT* [CLNT (3)]
- *WERKS* [CHAR (4)]
- FEVOR [CHAR (3)]

T024I
- *MANDT* [CLNT (3)]
- *IWERK* [CHAR (4)]
- INGRP [CHAR (3)]

T352R
- *MANDT* [CLNT (3)]
- *IWERK* [CHAR (4)]
- REVNR [CHAR (8)]

T353I
- *MANDT* [CLNT (3)]
- ILART [CHAR (3)]

T357
- *MANDT* [CLNT (3)]
- *WERKS* [CHAR (4)]
- BEBER [CHAR (3)]

T357M
- *MANDT* [CLNT (3)]
- ANLZU [CHAR (1)]

T370C
- *MANDT* [CLNT (3)]
- ABCKZ [CHAR (1)]

T499S
- *MANDT* [CLNT (3)]
- *WERKS* [CHAR (4)]
- STAND [CHAR (10)]

TCURC
- MANDT [CLNT (3)]
- WAERS [CUKY (5)]

TGSB
- MANDT [CLNT (3)]
- GSBER [CHAR (4)]

TKA01
- *MANDT* [CLNT (3)]
- KOKRS [CHAR (4)]

VBUK
- *MANDT* [CLNT (3)]
- VBELN [CHAR (10)]

VBUP
- *MANDT* [CLNT (3)]
- *VBELN* [CHAR (10)]
- POSNR [NUMC (6)]

RIHAUFKU-ANLUN = ANLA-ANLN2 0..N
RIHAUFKU-ANLNR = ANLH-ANLN1 0..N
RIHAUFKU-AUFNR = AUFK-AUFNR 0..N
RIHAUFKU-LEAD_AUFNR = AUFK-AUFNR 0..N
RIHAUFKU-MAUFNR = AUFK-AUFNR 0..N
RIHAUFKU-KOSTL = CSKS-KOSTL 0..N
RIHAUFKU-KOSTV = CSKS-KOSTL 0..N
RIHAUFKU-EQUNR = EQUI-EQUNR 0..N
RIHAUFKU-TPLNR = IFLOT-TPLNR 0..N
RIHAUFKU-KUNUM = KNA1-KUNNR 0..N
RIHAUFKU-BAUTL = MARA-MATNR 0..N
RIHAUFKU-WARPL = MPLA-WARPL 0..N
RIHAUFKU-OBJNR = ONR00-OBJNR 0..N
RIHAUFKU-QMNUM = QMEL-QMNUM 0..N
RIHAUFKU-MANDT = T000-MANDT 0..N
RIHAUFKU-BUKRS = T001-BUKRS 0..N
RIHAUFKU-AWERK = T001W-WERKS 0..N
RIHAUFKU-IWERK = T001W-WERKS 0..N
RIHAUFKU-SWERK = T001W-WERKS 0..N
RIHAUFKU-WERKS = T001W-WERKS 0..N
RIHAUFKU-AUART = T003O-AUART 0..N
RIHAUFKU-APGRP = T024A-FEVOR 0..N
RIHAUFKU-FEVOR = T024A-FEVOR 0..N
RIHAUFKU-INGPR = T024I-INGRP 0..N
RIHAUFKU-REVNR = T352R-REVNR 0..N
RIHAUFKU-ILART = T353I-ILART 0..N
RIHAUFKU-BEBER = T357-BEBER 0..N
RIHAUFKU-ANLZU = T357M-ANLZU 0..N
RIHAUFKU-ABCKZ = T370C-ABCKZ 0..N
RIHAUFKU-STORT = T499S-STAND 0..N
RIHAUFKU-WAERS = TCURC-WAERS 0..N
RIHAUFKU-GSBER = TGSB-GSBER 0..N
RIHAUFKU-KOKRS = TKA01-KOKRS 0..N
RIHAUFKU-KDAUF = VBUK-VBELN 0..N
RIHAUFKU-KDPOS = VBUP-POSNR 0..N