SAP ABAP table /CUM/VIAUF_IFLOS {Generated Table for View}


/CUM/VIAUF_IFLOS-/CUM/CUGUID = /CUM/AFCU-CUGUID
_CUM_AFCU
MANDT [CLNT (3)]
CUGUID [RAW (16)]
/CUM/VIAUF_IFLOS-AUFNR = AUFK-AUFNR
AUFK
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
/CUM/VIAUF_IFLOS-ARBID = CRID-OBJID
CRID
MANDT [CLNT (3)]
OBJTY [CHAR (2)]
OBJID [NUMC (8)]
/CUM/VIAUF_IFLOS-SAKTO = CSKA-KSTAR
CSKA
MANDT [CLNT (3)]
KTOPL [CHAR (4)]
KSTAR [CHAR (10)]
/CUM/VIAUF_IFLOS-BNFPO = EBAN-BNFPO
EBAN
MANDT [CLNT (3)]
BANFN [CHAR (10)]
BNFPO [NUMC (5)]
/CUM/VIAUF_IFLOS-INFNR = EINA-INFNR
EINA
MANDT [CLNT (3)]
INFNR [CHAR (10)]
/CUM/VIAUF_IFLOS-EQUNR = EQUI-EQUNR
EQUI
MANDT [CLNT (3)]
EQUNR [CHAR (18)]
/CUM/VIAUF_IFLOS-ALKEY = IFLOALT-ALKEY
IFLOALT
MANDT [CLNT (3)]
ALKEY [CHAR (1)]
/CUM/VIAUF_IFLOS-TPLNR_INT = IFLOT-TPLNR
IFLOT
MANDT [CLNT (3)]
TPLNR [CHAR (30)]
/CUM/VIAUF_IFLOS-LIFNR = LFA1-LIFNR
LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]
/CUM/VIAUF_IFLOS-BAUTL = MARA-MATNR
MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]
/CUM/VIAUF_IFLOS-ISTRU = MARA-MATNR
/CUM/VIAUF_IFLOS-SERMAT = MARA-MATNR
ONR00
MANDT [CLNT (3)]
OBJNR [CHAR (22)]
/CUM/VIAUF_IFLOS-OBJNR = ONR00-OBJNR
/CUM/VIAUF_IFLOS-MANDT = T000-MANDT
T000
MANDT [CLNT (3)]
/CUM/VIAUF_IFLOS-BUKRS = T001-BUKRS
T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]
/CUM/VIAUF_IFLOS-SOWRK = T001W-WERKS
/CUM/VIAUF_IFLOS-SWERK = T001W-WERKS
/CUM/VIAUF_IFLOS-WERKS = T001W-WERKS
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
/CUM/VIAUF_IFLOS-TXTSP = T002-SPRAS
T002
SPRAS [LANG (1)]
/CUM/VIAUF_IFLOS-AUART = T003O-AUART
T003O
CLIENT [CLNT (3)]
AUART [CHAR (4)]
/CUM/VIAUF_IFLOS-ARBEH = T006-MSEHI
/CUM/VIAUF_IFLOS-DAUME = T006-MSEHI
/CUM/VIAUF_IFLOS-DAUNE = T006-MSEHI
/CUM/VIAUF_IFLOS-MEINH = T006-MSEHI
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
/CUM/VIAUF_IFLOS-MATKL = T023-MATKL
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
/CUM/VIAUF_IFLOS-EKGRP = T024-EKGRP
T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]
/CUM/VIAUF_IFLOS-EKORG = T024E-EKORG
T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]
/CUM/VIAUF_IFLOS-INGPR = T024I-INGRP
T024I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
INGRP [CHAR (3)]
/CUM/VIAUF_IFLOS-PRIOK = T356-PRIOK
T356
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
PRIOK [CHAR (1)]
/CUM/VIAUF_IFLOS-ARTPR = T356A-ARTPR
T356A
MANDT [CLNT (3)]
ARTPR [CHAR (2)]
/CUM/VIAUF_IFLOS-ANLZU = T357M-ANLZU
T357M
MANDT [CLNT (3)]
ANLZU [CHAR (1)]
/CUM/VIAUF_IFLOS-IWERK = T399I-IWERK
T399I
MANDT [CLNT (3)]
IWERK [CHAR (4)]
/CUM/VIAUF_IFLOS-LOGRP = T421-LOGRP
T421
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LOGRP [CHAR (3)]
/CUM/VIAUF_IFLOS-QUALF = T423-QUALF
T423
MANDT [CLNT (3)]
WERKS [CHAR (4)]
QUALF [CHAR (2)]
/CUM/VIAUF_IFLOS-STEUS = T430-STEUS
T430
MANDT [CLNT (3)]
PLNAW [CHAR (1)]
STEUS [CHAR (4)]
/CUM/VIAUF_IFLOS-KTSCH = T435-VLSCH
T435
MANDT [CLNT (3)]
VLSCH [CHAR (7)]
/CUM/VIAUF_IFLOS-STORT = T499S-STAND
T499S
MANDT [CLNT (3)]
WERKS [CHAR (4)]
STAND [CHAR (10)]
/CUM/VIAUF_IFLOS-BEMOT = TBMOT-BEMOT
TBMOT
MANDT [CLNT (3)]
BEMOT [CHAR (2)]
/CUM/VIAUF_IFLOS-SELKZ = TCK08-SELKZ
TCK08
MANDT [CLNT (3)]
SELKZ [CHAR (1)]
/CUM/VIAUF_IFLOS-WAERS = TCURC-WAERS
TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]
_CUM_VIAUF_IFLOS
MANDT [CLNT (3)]
AUFNR [CHAR (12)]
ILOAN [CHAR (12)]
AUFPL [NUMC (10)]
APLZL [NUMC (8)]
IPHAS [CHAR (1)]
PRIOK [CHAR (1)]
ARTPR [CHAR (2)]
EQUNR [CHAR (18)]
BAUTL [CHAR (18)]
INGPR [CHAR (3)]
IWERK [CHAR (4)]
INSPK [CHAR (12)]
ADDAT [DATS (8)]
AUART [CHAR (4)]
STORT [CHAR (10)]
SOWRK [CHAR (4)]
TPLNR [CHAR (40)]
EQFNR [CHAR (30)]
VORNR [CHAR (4)]
STEUS [CHAR (4)]
ARBID [NUMC (8)]
WERKS [CHAR (4)]
KTSCH [CHAR (7)]
LTXA1 [CHAR (40)]
LOANZ [DEC (3)]
LOART [CHAR (4)]
RSANZ [NUMC (3)]
QUALF [CHAR (2)]
ANZMA [DEC (5)]
LOGRP [CHAR (3)]
SUMNR [NUMC (8)]
LIFNR [CHAR (10)]
PREIS [CURR (11)]
PEINH [DEC (5)]
SAKTO [CHAR (10)]
WAERS [CUKY (5)]
INFNR [CHAR (10)]
EKORG [CHAR (4)]
EKGRP [CHAR (3)]
MATKL [CHAR (9)]
ANZZL [INT1 (3)]
PRZNT [INT1 (3)]
BUKRS [CHAR (4)]
INDET [CHAR (1)]
LARNT [CHAR (6)]
RUECK [NUMC (10)]
RMZHL [NUMC (8)]
OBJNR [CHAR (22)]
BANFN [CHAR (10)]
BNFPO [NUMC (5)]
SELKZ [CHAR (1)]
ANLZU [CHAR (1)]
ISTRU [CHAR (18)]
EBORT [CHAR (20)]
MEINH [UNIT (3)]
DAUNO [QUAN (5)]
DAUNE [UNIT (3)]
DAUMI [QUAN (5)]
DAUME [UNIT (3)]
EINSA [CHAR (1)]
EINSE [CHAR (1)]
ARBEI [QUAN (7)]
ARBEH [UNIT (3)]
ISMNW [QUAN (13)]
FSAVD [DATS (8)]
FSAVZ [TIMS (6)]
FSEDD [DATS (8)]
FSEDZ [TIMS (6)]
SSAVD [DATS (8)]
SSAVZ [TIMS (6)]
SSEDD [DATS (8)]
SSEDZ [TIMS (6)]
ISDD [DATS (8)]
ISDZ [TIMS (6)]
IEDD [DATS (8)]
IEDZ [TIMS (6)]
PUFFR [DEC (3)]
PUFGS [DEC (3)]
NTANF [DATS (8)]
NTANZ [TIMS (6)]
NTEND [DATS (8)]
NTENZ [TIMS (6)]
AUFKT [DEC (3)]
BEMOT [CHAR (2)]
ADRNRA [CHAR (10)]
ABLAD [CHAR (25)]
WEMPF [CHAR (12)]
SERMAT [CHAR (18)]
SERIALNR [CHAR (18)]
DEVICEID [CHAR (40)]
PERNR [NUMC (8)]
TXTSP [LANG (1)]
PHFLG [CHAR (1)]
QFMNW [QUAN (7)]
ALKEY [CHAR (1)]
VERSN [NUMC (3)]
TPLNR_INT [CHAR (30)]
SWERK [CHAR (4)]
_CUM_CUGUID [RAW (16)]
0..N
{0,1}
1
1,1
0..N
0..N
0..N