SAP ABAP table /RPM/TS_ITEM_API_COLUMN {Portfolio Item Attributes for Reporting: Column Chart}


/RPM/TS_ITEM_API_COLUMN-UNIT = /RPM/CAP_UNITS-UNIT
_RPM_CAP_UNITS
CLIENT [CLNT (3)]
UNIT [UNIT (3)]
/RPM/TS_ITEM_API_COLUMN-CURRENCY = /RPM/CURRENCY-CURRENCY
_RPM_CURRENCY
CLIENT [CLNT (3)]
CURRENCY [CUKY (5)]
/RPM/TS_ITEM_API_COLUMN-ITEM_TYPE = /RPM/ITEM_TYPE-ITEM_TYPE
_RPM_ITEM_TYPE
CLIENT [CLNT (3)]
ITEM_TYPE [CHAR (15)]
/RPM/TS_ITEM_API_COLUMN-CAP_PERIODTYPE = /RPM/PERIOD_TYPE-PERIODTYPE
_RPM_PERIOD_TYPE
CLIENT [CLNT (3)]
PERIODTYPE [NUMC (2)]
/RPM/TS_ITEM_API_COLUMN-PERIODTYPE = /RPM/PERIOD_TYPE-PERIODTYPE
_RPM_TS_ITEM_API_COLUMN
ITEM_TYPE [CHAR (15)]
CATEGORY [NUMC (4)]
SUBCATEGORY [NUMC (4)]
PHASE [NUMC (4)]
PTYPE [NUMC (4)]
TTYPE [NUMC (4)]
CURRENCY [CUKY (5)]
LOCATION [CHAR (4)]
GEOGRAPHY [CHAR (4)]
PERIODTYPE [NUMC (2)]
UNIT [UNIT (3)]
PRIORITY_GROUP [NUMC (2)]
STATUS [CHAR (5)]
CAP_PERIODTYPE [NUMC (2)]
/RPM/TS_ITEM_API_COLUMN-STATUS = /RPM/STATUS-STATUS
_RPM_STATUS
CLIENT [CLNT (3)]
STATUS [CHAR (5)]
/RPM/TS_ITEM_API_COLUMN-GEOGRAPHY = DPR_AREA-AREA
DPR_AREA
MANDT [CLNT (3)]
AREA [CHAR (4)]
/RPM/TS_ITEM_API_COLUMN-LOCATION = DPR_LOCATION-LOCATION
DPR_LOCATION
MANDT [CLNT (3)]
LOCATION [CHAR (4)]
/RPM/TS_ITEM_API_COLUMN-CATEGORY = RPM_PROJ_CAT-CATEGORY
RPM_PROJ_CAT
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
/RPM/TS_ITEM_API_COLUMN-PHASE = RPM_PROJ_PHASE-PHASE
RPM_PROJ_PHASE
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
PHASE [NUMC (4)]
/RPM/TS_ITEM_API_COLUMN-PRIORITY_GROUP = RPM_PROJ_PRGRP-PRIORITY_GROUP
RPM_PROJ_PRGRP
MANDT [CLNT (3)]
PRIORITY_GROUP [NUMC (2)]
/RPM/TS_ITEM_API_COLUMN-SUBCATEGORY = RPM_PROJ_SUBCAT-SUBCATEGORY
RPM_PROJ_SUBCAT
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
SUBCATEGORY [NUMC (4)]
/RPM/TS_ITEM_API_COLUMN-TTYPE = RPM_PROJ_TTYPE-TTYPE
RPM_PROJ_TTYPE
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
TTYPE [NUMC (4)]
/RPM/TS_ITEM_API_COLUMN-PTYPE = RPM_PROJ_TYPE-PTYPE
RPM_PROJ_TYPE
MANDT [CLNT (3)]
CATEGORY [NUMC (4)]
PTYPE [NUMC (4)]
0..N
1
1
1