SAP ABAP table BMMH1 {Material Master: Transfer of Main Data}




BMMH1-RDPRF = RDPR-RDPRF
0..N
RDPR
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RDPRF [CHAR (4)]
RDZAE [NUMC (6)]
BMMH1-LGFSB = T001L-LGORT
0..N
T001L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LGORT [CHAR (4)]
BMMH1-LGPRO = T001L-LGORT
0..N
BMMH1-DWERK = T001W-WERKS
0..N
T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]
BMMH1-VPWRK = T001W-WERKS
0..N
BMMH1-VRBWK = T001W-WERKS
0..N
BMMH1-HERKL = T005-LAND1
0..N
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BMMH1-HERKR = T005S-BLAND
0..N
T005S
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BLAND [CHAR (3)]
BMMH1-AUSME = T006-MSEHI
BMMH1-BEZME = T006-MSEHI
BMMH1-BSTME = T006-MSEHI
BMMH1-EHOFFB = T006-MSEHI
BMMH1-EHOFFE = T006-MSEHI
BMMH1-ERGEI = T006-MSEHI
BMMH1-ERVOE = T006-MSEHI
BMMH1-FRTME = T006-MSEHI
BMMH1-GEWEI = T006-MSEHI
BMMH1-LHME1 = T006-MSEHI
BMMH1-LHME2 = T006-MSEHI
BMMH1-LHME3 = T006-MSEHI
BMMH1-LVSME = T006-MSEHI
BMMH1-LZEIH = T006-MSEHI
BMMH1-MEABM = T006-MSEHI
BMMH1-MEINS = T006-MSEHI
BMMH1-SCHME = T006-MSEHI
BMMH1-VOLEH = T006-MSEHI
0..N
T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]
0..N
T009
MANDT [CLNT (3)]
PERIV [CHAR (2)]
0..N
T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]
0..N
T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]
0..N
T024D
MANDT [CLNT (3)]
WERKS [CHAR (4)]
DISPO [CHAR (3)]
0..N
T024F
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FEVOR [CHAR (3)]
0..N
T024L
MANDT [CLNT (3)]
LABOR [CHAR (3)]
0..N


BMMH1
MEINS [UNIT (3)]
MATKL [CHAR (9)]
LABOR [CHAR (3)]
GEWEI [UNIT (3)]
VOLEH [UNIT (3)]
SPART [CHAR (2)]
VRKME [UNIT (3)]
VMSTA [CHAR (2)]
DWERK [CHAR (4)]
SCHME [UNIT (3)]
VERSG [CHAR (1)]
BONUS [CHAR (2)]
BMMH1-VRKME = T006-MSEHI
BMMH1-PERIV = T009-PERIV
BMMH1-MATKL = T023-MATKL
BMMH1-EKGRP = T024-EKGRP
BMMH1-DISPO = T024D-DISPO
BMMH1-FEVOR = T024F-FEVOR
BMMH1-LABOR = T024L-LABOR
BMMH1-BKLAS = T025-BKLAS
BMMH1-EKLAS = T025-BKLAS
BMMH1-QKLAS = T025-BKLAS
BMMH1-VJBKL = T025-BKLAS
BMMH1-VMBKL = T025-BKLAS
BMMH1-MMSTA = T141-MMSTA
BMMH1-MSTAE = T141-MMSTA
BMMH1-RAUBE = T142-RAUBE
BMMH1-TEMPB = T143-TEMPB
BMMH1-BEHVO = T144-BEHVO
BMMH1-BWTTY = T149C-BWTTY
BMMH1-ABCIN = T159C-ABCIN
BMMH1-KONDM = T178-KONDM
BMMH1-PRDHA = T179-PRODH
BMMH1-PRODH = T179-PRODH
BMMH1-KOSCH = T190S-KOSCH
BMMH1-PLKPT = T301-LGTYP
BMMH1-LGBKZ = T304-LGBKZ
BMMH1-LTKZA = T305-LGTKZ
BMMH1-LTKZE = T305-LGTKZ
T025
MANDT [CLNT (3)]
BKLAS [CHAR (4)]
T141
MANDT [CLNT (3)]
MMSTA [CHAR (2)]
T142
MANDT [CLNT (3)]
RAUBE [CHAR (2)]
T143
MANDT [CLNT (3)]
TEMPB [CHAR (2)]
T144
MANDT [CLNT (3)]
BEHVO [CHAR (2)]
T149C
MANDT [CLNT (3)]
BWTTY [CHAR (1)]
T159C
MANDT [CLNT (3)]
WERKS [CHAR (4)]
ABCIN [CHAR (1)]
T178
MANDT [CLNT (3)]
KONDM [CHAR (2)]
T179
MANDT [CLNT (3)]
PRODH [CHAR (18)]
T190S
MANDT [CLNT (3)]
KOSCH [CHAR (18)]
T301
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
T304
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGBKZ [CHAR (3)]
T305
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTKZ [CHAR (3)]
0..N

PROVG [CHAR (2)]
MTPOS [CHAR (4)]
PRODH [CHAR (18)]
PMATN [CHAR (18)]
KONDM [CHAR (2)]
KTGRM [CHAR (2)]
TATY1 [CHAR (4)]
TAXM1 [CHAR (1)]
TATY2 [CHAR (4)]
TAXM2 [CHAR (1)]
TATY3 [CHAR (4)]
TAXM3 [CHAR (1)]
TATY4 [CHAR (4)]
TAXM4 [CHAR (1)]
TATY5 [CHAR (4)]
TAXM5 [CHAR (1)]
TATY6 [CHAR (4)]
TAXM6 [CHAR (1)]
TATY7 [CHAR (4)]
TAXM7 [CHAR (1)]
TATY8 [CHAR (4)]
TAXM8 [CHAR (1)]
TATY9 [CHAR (4)]
TAXM9 [CHAR (1)]
TRAGR [CHAR (4)]
LADGR [CHAR (4)]
MMSTA [CHAR (2)]
BSTME [UNIT (3)]
EKWSL [CHAR (4)]
EKGRP [CHAR (3)]
USEQU [CHAR (1)]
SOBSL [CHAR (2)]
DISMM [CHAR (2)]
DISPO [CHAR (3)]
PERIV [CHAR (2)]
FHORI [CHAR (3)]
DISLS [CHAR (2)]
LAGPR [CHAR (1)]
MAABC [CHAR (1)]
AUFTL [CHAR (1)]
MTVFP [CHAR (2)]
GEWGR [CHAR (2)]
FEVOR [CHAR (3)]
AUSME [UNIT (3)]
BEHVO [CHAR (2)]
RAUBE [CHAR (2)]
TEMPB [CHAR (2)]
STOFF [CHAR (18)]

BMMH1-BSSKZ = T306-BSSKZ (0..N, 0..N)

T306
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
BSSKZ [CHAR (1)]

BMMH1-LETY1 = T307-LETYP (0..N, 0..N)
BMMH1-LETY2 = T307-LETYP (0..N, 0..N)
BMMH1-LETY3 = T307-LETYP (0..N, 0..N)

T307
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LETYP [CHAR (3)]

BMMH1-KOBER = T30A-KOBER (0..N, 0..N)

T30A
MANDT [CLNT (3)]
LGNUM [CHAR (3)]
LGTYP [CHAR (3)]
KOBER [CHAR (3)]

BMMH1-RBNRM = T352B-RBNR (0..N, 0..N)

T352B
MANDT [CLNT (3)]
RBNR [CHAR (9)]

BMMH1-SERNP = T377P-SERAIL (0..N, 0..N)

T377P
MANDT [CLNT (3)]
SERAIL [CHAR (4)]

BMMH1-EKWSL = T405-EKWSL (0..N, 0..N)

T405
MANDT [CLNT (3)]
EKWSL [CHAR (4)]

BMMH1-STLAN = T416-STLAN (0..N, 0..N)

T416
MANDT [CLNT (3)]
STLAN [CHAR (1)]

BMMH1-KTSCH = T435-VLSCH (0..N, 0..N)

T435
MANDT [CLNT (3)]
VLSCH [CHAR (7)]

BMMH1-FHORI = T436A-FHORI (0..N, 0..N)

T436A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
FHORI [CHAR (3)]

BMMH1-EPRIO = T437E-EPRIO (0..N, 0..N)

T437E
MANDT [CLNT (3)]
EPRIO [CHAR (4)]
RFOLG [NUMC (2)]


LZEIH [UNIT (3)]
LVSME [UNIT (3)]
LHME1 [UNIT (3)]
LHME2 [UNIT (3)]
LHME3 [UNIT (3)]
LETY1 [CHAR (3)]
LETY2 [CHAR (3)]
LETY3 [CHAR (3)]
LGBKZ [CHAR (3)]
LTKZE [CHAR (3)]
LTKZA [CHAR (3)]
LGPLA [CHAR (10)]
BWTTY [CHAR (1)]
MYPOL [CHAR (4)]
BKLAS [CHAR (4)]
VMBKL [CHAR (4)]
VJBKL [CHAR (4)]
STAWN [CHAR (17)]
HERKL [CHAR (3)]
HERKR [CHAR (3)]
MTVER [CHAR (4)]
NUMTP [CHAR (2)]
MEABM [UNIT (3)]
STEUF [CHAR (4)]
FGRU1 [CHAR (4)]
FGRU2 [CHAR (4)]
PLANV [CHAR (3)]
KTSCH [CHAR (7)]
BZOFFB [CHAR (2)]
EHOFFB [UNIT (3)]
BZOFFE [CHAR (2)]
EHOFFE [UNIT (3)]
MGFORM [CHAR (6)]
EWFORM [CHAR (6)]
PRCTR [CHAR (10)]
BSSKZ [CHAR (1)]
KUNNR [CHAR (10)]
PRDHA [CHAR (18)]
HRKFT [CHAR (4)]
STLAN [CHAR (1)]
SOBSK [CHAR (2)]
KOSGR [CHAR (10)]
ETIAR [CHAR (2)]
ETIFO [CHAR (2)]
ERGEI [UNIT (3)]
ERVOE [UNIT (3)]
MRPPP [CHAR (3)]
FRTME [UNIT (3)]
LGPRO [CHAR (4)]
DISGR [CHAR (4)]
QZGTP [CHAR (4)]
SSQSS [CHAR (8)]
VPMAT [CHAR (18)]
VPWRK [CHAR (4)]
BMMH1-SFEPR = T437S-SFPRO
0..N
0..N
T437S
MANDT [CLNT (3)]
SFPRO [CHAR (4)]
BMMH1-DISMM = T438A-DISMM
0..N
0..N
T438A
MANDT [CLNT (3)]
DISMM [CHAR (2)]
BMMH1-DISGR = T438M-MTART
0..N
0..N
T438M
MANDT [CLNT (3)]
WERKS [CHAR (4)]
MTART [CHAR (4)]
BMMH1-RWPRO = T438R-RWPRO
0..N
0..N
T438R
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RWPRO [CHAR (3)]
BMMH1-DISLS = T439A-DISLS
0..N
0..N
T439A
MANDT [CLNT (3)]
DISLS [CHAR (2)]
BMMH1-LFRHY = T439G-MRPPP
0..N
0..N
BMMH1-MRPPP = T439G-MRPPP
0..N
0..N
T439G
MANDT [CLNT (3)]
WERKS [CHAR (4)]
MRPPP [CHAR (3)]
BMMH1-LAGPR = T439L-LAGPR
0..N
0..N
T439L
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LAGPR [CHAR (1)]
BMMH1-AUFTL = T439P-AUFTL
0..N
0..N
T439P
MANDT [CLNT (3)]
WERKS [CHAR (4)]
PERKZ [CHAR (1)]
AUFTL [CHAR (1)]
BMMH1-GEWGR = T440G-GEWGR
0..N
0..N
T440G
MANDT [CLNT (3)]
GEWGR [CHAR (2)]
COUN2 [CHAR (2)]
BMMH1-LSOBS = T460A-SOBSL
0..N
0..N
BMMH1-SOBSK = T460A-SOBSL
0..N
0..N
BMMH1-SOBSL = T460A-SOBSL
0..N
0..N
T460A
MANDT [CLNT (3)]
WERKS [CHAR (4)]
SOBSL [CHAR (2)]
BMMH1-STRGR = T461P-STRGR
0..N
0..N
T461P
MANDT [CLNT (3)]
STRGR [CHAR (2)]

RWPRO [CHAR (3)]
ABCIN [CHAR (1)]
AWSLS [CHAR (6)]
SERNP [CHAR (4)]
SFEPR [CHAR (4)]
VHART [CHAR (4)]
MAGRV [CHAR (4)]
RBNRM [CHAR (9)]
QSSYS [CHAR (4)]
LFRHY [CHAR (3)]
RDPRF [CHAR (4)]
VRBMT [CHAR (18)]
VRBWK [CHAR (4)]
STRGR [CHAR (2)]
EPRIO [CHAR (4)]
NFMAT [CHAR (18)]
LSOBS [CHAR (2)]
BEZME [UNIT (3)]
MVGR1 [CHAR (3)]
MVGR2 [CHAR (3)]
MVGR3 [CHAR (3)]
MVGR4 [CHAR (3)]
MVGR5 [CHAR (3)]
QMATA [CHAR (6)]
TAXIM [CHAR (1)]
PLNTY [CHAR (1)]
LGFSB [CHAR (4)]
SFCPF [CHAR (6)]
MDACH [CHAR (2)]
KOSCH [CHAR (18)]
MFRGR [CHAR (8)]
BMATN [CHAR (18)]
MFRNR [CHAR (10)]
MPROF [CHAR (4)]
MSTAE [CHAR (2)]
MSTAV [CHAR (2)]
PROFL [CHAR (3)]
CASNR [CHAR (15)]
FVIDK [CHAR (4)]
GPNUM [CHAR (9)]
LOGGR [CHAR (4)]
MOGRU [CHAR (6)]
MOWNR [CHAR (12)]
STEUC [CHAR (16)]
EKLAS [CHAR (4)]
QKLAS [CHAR (4)]
PLKPT [CHAR (3)]
KOBER [CHAR (3)]
VSPVB [CHAR (10)]
CONVT [CHAR (2)]
PACKCODE [CHAR (10)]
DG_PACK_STATUS [CHAR (10)]
ANP [CHAR (9)]
COMMODITY [CHAR (18)]

BMMH1-MDACH = T46AC-MDACH

BMMH1-STAWN = T604-STAWN

BMMH1-STEUC = T604F-STEUC

BMMH1-GPNUM = T609G-GPNUM

BMMH1-CASNR = T610C-CASNR

BMMH1-MOGRU = T618G-MOGRU

BMMH1-MOWNR = T618M-MOWNR

BMMH1-TATY1 = T685-KSCHL

BMMH1-TATY2 = T685-KSCHL

BMMH1-TATY3 = T685-KSCHL

BMMH1-TATY4 = T685-KSCHL

BMMH1-TATY5 = T685-KSCHL

BMMH1-TATY6 = T685-KSCHL

BMMH1-TATY7 = T685-KSCHL

BMMH1-TATY8 = T685-KSCHL

BMMH1-TATY9 = T685-KSCHL

BMMH1-ETIAR = T6WP3-ETIAR

BMMH1-ETIFO = T6WP4-ETIFO

BMMH1-COMMODITY = TBAC_PHYSCOMM-COMMODITY

0..N

T46AC

MANDT [CLNT (3)]
MDACH [CHAR (2)]
ACCFM [CHAR (4)]
ACCTO [CHAR (4)]

T604

MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STAWN [CHAR (17)]

T604F

MANDT [CLNT (3)]
LAND1 [CHAR (3)]
STEUC [CHAR (16)]

T609G

MANDT [CLNT (3)]
LAND1 [CHAR (3)]
GPNUM [CHAR (9)]

T610C

MANDT [CLNT (3)]
LAND1 [CHAR (3)]
CASNR [CHAR (15)]

T618G

MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOGRU [CHAR (6)]

T618M

MANDT [CLNT (3)]
LAND1 [CHAR (3)]
MOWNR [CHAR (12)]

T685

MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KSCHL [CHAR (4)]

T6WP3

MANDT [CLNT (3)]
ETIAR [CHAR (2)]

T6WP4

MANDT [CLNT (3)]
ETIFO [CHAR (2)]

TBAC_PHYSCOMM

CLIENT [CLNT (3)]
COMMODITY [CHAR (18)]


BMMH1-PLANV = TC23-PLANV
TC23
MANDT [CLNT (3)]
PLANV [CHAR (3)]
0..N
BMMH1-EWFORM = TC25-IDENT
BMMH1-MGFORM = TC25-IDENT
TC25
MANDT [CLNT (3)]
IDENT [CHAR (6)]
0..N
0..N
BMMH1-PLNTY = TCA01-PLNTY
TCA01
MANDT [CLNT (3)]
PLNTY [CHAR (1)]
0..N
BMMH1-BZOFFB = TCA54-BZOFF
BMMH1-BZOFFE = TCA54-BZOFF
TCA54
BZOFF [CHAR (2)]
0..N
0..N
BMMH1-STEUF = TCF10-STEUF
TCF10
MANDT [CLNT (3)]
STEUF [CHAR (4)]
0..N
BMMH1-FGRU1 = TCF12-FGRUA
BMMH1-FGRU2 = TCF12-FGRUA
TCF12
MANDT [CLNT (3)]
FGRUA [CHAR (4)]
0..N
0..N
BMMH1-KOSGR = TCK14-KOSGR
TCK14
MANDT [CLNT (3)]
BWKEY [CHAR (4)]
KOSGR [CHAR (10)]
0..N
BMMH1-SFCPF = TCO43-CO_PRODPRF
TCO43
MANDT [CLNT (3)]
WERKS [CHAR (4)]
CO_PRODPRF [CHAR (6)]
0..N
BMMH1-CONVT = TCSCP_CONV_TYPE-CONV_TYPE
TCSCP_CONV_TYPE
MANDT [CLNT (3)]
CONV_TYPE [CHAR (2)]
0..N
BMMH1-DG_PACK_STATUS = TDG101-DG_PACK_STATUS
TDG101
MANDT [CLNT (3)]
DG_PACK_STATUS [CHAR (10)]
0..N
BMMH1-PROFL = TDG41-PROFL
TDG41
MANDT [CLNT (3)]
PROFL [CHAR (3)]
0..N
BMMH1-HRKFT = TKKH1-HRKFT
TKKH1
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOATY [CHAR (2)]
HRKFT [CHAR (4)]
0..N
BMMH1-AWSLS = TKV01-AWSLS
TKV01
MANDT [CLNT (3)]
AWOBA [CHAR (2)]
AWSLS [CHAR (6)]
0..N
BMMH1-LADGR = TLGR-LADGR


TLGR
MANDT [CLNT (3)]
LADGR [CHAR (4)]
BMMH1-LOGGR = TLOG-LOGGR
0..N
TLOG
MANDT [CLNT (3)]
LOGGR [CHAR (4)]
BMMH1-MAABC = TMABC-MAABC
0..N
TMABC
MANDT [CLNT (3)]
MAABC [CHAR (1)]
BMMH1-MFRGR = TMFG-MFRGR
0..N
TMFG
MANDT [CLNT (3)]
MFRGR [CHAR (8)]
BMMH1-TAXIM = TMKM1-TAXIM
0..N
TMKM1
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
TAXIM [CHAR (1)]
BMMH1-MPROF = TMPPF-MPROF
0..N
TMPPF
MANDT [CLNT (3)]
MPROF [CHAR (4)]
BMMH1-USEQU = TMQ2-USEQU
0..N
TMQ2
MANDT [CLNT (3)]
USEQU [CHAR (1)]
BMMH1-MTVFP = TMVF-MTVFP
0..N
TMVF
MANDT [CLNT (3)]
MTVFP [CHAR (2)]
BMMH1-NUMTP = TNTP-NUMTP
0..N
TNTP
MANDT [CLNT (3)]
NUMTP [CHAR (2)]
BMMH1-MYPOL = TPOOL-MYPOOL
0..N
TPOOL
MANDT [CLNT (3)]
MYKEY [CHAR (4)]
MYPOOL [CHAR (4)]
BMMH1-MTPOS = TPTM-MTPOS
0..N
TPTM
MANDT [CLNT (3)]
MTPOS [CHAR (4)]
BMMH1-QMATA = TQ01B-QMATAUTH
0..N
TQ01B
MANDT [CLNT (3)]
QMATAUTH [CHAR (6)]
BMMH1-QSSYS = TQ02-QSSYS
0..N
TQ02
MANDT [CLNT (3)]
QSSYS [CHAR (4)]
BMMH1-QZGTP = TQ05-ZGTYP
BMMH1-SSQSS = TQ08-QM_PUR
BMMH1-TAXM1 = TSKM-TAXKM
BMMH1-TAXM2 = TSKM-TAXKM


BMMH1-TAXM3 = TSKM-TAXKM
BMMH1-TAXM4 = TSKM-TAXKM
BMMH1-TAXM5 = TSKM-TAXKM
BMMH1-TAXM6 = TSKM-TAXKM
BMMH1-TAXM7 = TSKM-TAXKM
BMMH1-TAXM8 = TSKM-TAXKM
BMMH1-TAXM9 = TSKM-TAXKM
BMMH1-SPART = TSPA-SPART
BMMH1-TRAGR = TTGR-TRAGR
BMMH1-BONUS = TVBO-BONUS
BMMH1-MAGRV = TVEGR-MAGRV
BMMH1-MTVER = TVFM-MTVER
BMMH1-KTGRM = TVKM-KTGRM
BMMH1-MVGR1 = TVM1-MVGR1
BMMH1-MVGR2 = TVM2-MVGR2
BMMH1-MVGR3 = TVM3-MVGR3
BMMH1-MVGR4 = TVM4-MVGR4
BMMH1-MVGR5 = TVM5-MVGR5
BMMH1-MSTAV = TVMS-VMSTA
0..N
TQ05
MANDT [CLNT (3)]
ZGTYP [CHAR (4)]
TQ08
MANDT [CLNT (3)]
QM_PUR [CHAR (8)]
TSKM
MANDT [CLNT (3)]
TATYP [CHAR (4)]
TAXKM [CHAR (1)]
TSPA
MANDT [CLNT (3)]
SPART [CHAR (2)]
TTGR
MANDT [CLNT (3)]
TRAGR [CHAR (4)]
TVBO
MANDT [CLNT (3)]
BONUS [CHAR (2)]
TVEGR
MANDT [CLNT (3)]
MAGRV [CHAR (4)]
TVFM
MANDT [CLNT (3)]
MTVER [CHAR (4)]
TVKM
MANDT [CLNT (3)]
KTGRM [CHAR (2)]
TVM1
MANDT [CLNT (3)]
MVGR1 [CHAR (3)]
TVM2
MANDT [CLNT (3)]
MVGR2 [CHAR (3)]
TVM3
MANDT [CLNT (3)]
MVGR3 [CHAR (3)]
TVM4
MANDT [CLNT (3)]
MVGR4 [CHAR (3)]
TVM5
MANDT [CLNT (3)]
MVGR5 [CHAR (3)]


BMMH1-VMSTA = TVMS-VMSTA
0..N
0..N
TVMS
MANDT [CLNT (3)]
VMSTA [CHAR (2)]
BMMH1-PROVG = TVPR-PROVG
0..N
TVPR
MANDT [CLNT (3)]
PROVG [CHAR (2)]
BMMH1-VERSG = TVSM-STGMA
0..N
TVSM
MANDT [CLNT (3)]
STGMA [CHAR (1)]
BMMH1-VHART = TVTY-TRATY
0..N
TVTY
MANDT [CLNT (3)]
TRATY [CHAR (4)]