SAP ABAP table BUR_DI {BPR: Transfer Structure (Direct Input)}


BUR_DI-FAX_CNTRY = T005-LAND1
0..N
T005
MANDT [CLNT (3)]
LAND1 [CHAR (3)]
BUR_DI-TEL_CNTRY = T005-LAND1
0..N
TB905
CLIENT [CLNT (3)]
RELKIND [CHAR (4)]
XRF [CHAR (1)]
BUR_DI-RELKIND = TB905-RELKIND
0..N
TB910
CLIENT [CLNT (3)]
ABTNR [CHAR (4)]
BUR_DI-ABTNR = TB910-ABTNR
0..N
TB912
CLIENT [CLNT (3)]
PAFKT [CHAR (4)]
BUR_DI-PAFKT = TB912-PAFKT
0..N
TB914
CLIENT [CLNT (3)]
PAAUTH [CHAR (1)]
BUR_DI-PAAUTH = TB914-PAAUTH
0..N
TB916
CLIENT [CLNT (3)]
PAVIP [CHAR (1)]
BUR_DI-PAVIP = TB916-PAVIP
0..N
TBZ0
CLIENT [CLNT (3)]
OBJAP [CHAR (4)]
RLTYP [CHAR (6)]
BUR_DI-RLTYP = TBZ0-RLTYP
0..N
TBZ9
CLIENT [CLNT (3)]
RELTYP [CHAR (6)]
XRF [CHAR (1)]
BUR_DI-RELTYP = TBZ9-RELTYP
0..N
TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]
BUR_DI-CMPY_PART_CUR = TCURC-WAERS
0..N
BUR_DI-REL_CUR = TCURC-WAERS
0..N
TSAC
COMM_TYPE [CHAR (3)]
BUR_DI-DEFLT_COMM = TSAC-COMM_TYPE
0..N
BUR_DI
RELTYP [CHAR (6)]
RLTYP [CHAR (6)]
RELKIND [CHAR (4)]
PAFKT [CHAR (4)]
ABTNR [CHAR (4)]
PAAUTH [CHAR (1)]
PAVIP [CHAR (1)]
REL_CUR [CUKY (5)]
ADDRNUMBER [CHAR (10)]
DEFLT_COMM [CHAR (3)]
TEL_CNTRY [CHAR (3)]
FAX_CNTRY [CHAR (3)]
CMPY_PART_CUR [CUKY (5)]
1
1
1