SAP ABAP table CAPP_OPR {Process data}

CAPP_OPR
MANDT [CLNT (3)]
PLNTY [CHAR (1)]
AENNR [CHAR (12)]
STEUS [CHAR (4)]
WERKS [CHAR (4)]
KTSCH [CHAR (7)]
TXTSP [LANG (1)]
MEINH [UNIT (3)]
ZEIER [UNIT (3)]
LAR01 [CHAR (6)]
VGE01 [UNIT (3)]
LAR02 [CHAR (6)]
VGE02 [UNIT (3)]
LAR03 [CHAR (6)]
VGE03 [UNIT (3)]
LAR04 [CHAR (6)]
VGE04 [UNIT (3)]
LAR05 [CHAR (6)]
VGE05 [UNIT (3)]
LAR06 [CHAR (6)]
VGE06 [UNIT (3)]
ZERMA [CUKY (5)]
PDEST [CHAR (4)]
QUALF [CHAR (2)]
RFGRP [CHAR (10)]
RFSCH [CHAR (10)]
RASCH [CHAR (2)]
LOGRP [CHAR (3)]
ZEIMU [UNIT (3)]
ZEIMB [UNIT (3)]
ZEILM [UNIT (3)]
ZEILP [UNIT (3)]
ZEIWN [UNIT (3)]
ZEIWM [UNIT (3)]
ZEITN [UNIT (3)]
ZEITM [UNIT (3)]
RSTRA [CHAR (2)]
BZOFFB [CHAR (2)]
EHOFFB [UNIT (3)]
BZOFFE [CHAR (2)]
EHOFFE [UNIT (3)]
LIFNR [CHAR (10)]
SAKTO [CHAR (10)]
WAERS [CUKY (5)]
INFNR [CHAR (10)]
EKORG [CHAR (4)]
EKGRP [CHAR (3)]
MATKL [CHAR (9)]
DAUNE [UNIT (3)]
DAUME [UNIT (3)]
ARBEH [UNIT (3)]
VERTL [CHAR (2)]
MLSTN [CHAR (5)]
BUKRS [CHAR (4)]
SLWID [CHAR (7)]
USE04 [UNIT (3)]
USE05 [UNIT (3)]
USE06 [CUKY (5)]
USE07 [CUKY (5)]
ANFKO [CHAR (10)]
ANFKOKRS [CHAR (4)]
KAPAR [CHAR (3)]
LARNT [CHAR (6)]
QRASTEREH [UNIT (3)]
ANLZU [CHAR (1)]
ISTRU [CHAR (18)]
KALID [CHAR (2)]
VERTN [CHAR (8)]
ZGR01 [CHAR (3)]
ZGR02 [CHAR (3)]
ZGR03 [CHAR (3)]
ZGR04 [CHAR (3)]
ZGR05 [CHAR (3)]
ZGR06 [CHAR (3)]
RUZUS [CHAR (4)]
BMEIH [UNIT (3)]
CKSELKZ [CHAR (1)]
NPRIO [CHAR (1)]
PHSEQ [CHAR (2)]
PSPNR [NUMC (8)]
QLOTYPE [CHAR (2)]
QLKAPAR [CHAR (3)]
EBELP [NUMC (5)]
RFPNT [CHAR (20)]

CAPP_OPR-AENNR = AENR-AENNR 0..N

AENR
MANDT [CLNT (3)]
AENNR [CHAR (12)]

CAPP_OPR-SAKTO = CSKA-KSTAR 0..N

CSKA
MANDT [CLNT (3)]
KTOPL [CHAR (4)]
KSTAR [CHAR (10)]

CAPP_OPR-ANFKO = CSKS-KOSTL 0..N

CSKS
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
KOSTL [CHAR (10)]
DATBI [DATS (8)]

CAPP_OPR-LAR01 = CSLA-LSTAR

CAPP_OPR-LAR02 = CSLA-LSTAR 0..N

CAPP_OPR-LAR03 = CSLA-LSTAR 0..N

CAPP_OPR-LAR04 = CSLA-LSTAR 0..N

CAPP_OPR-LAR05 = CSLA-LSTAR

CAPP_OPR-LAR06 = CSLA-LSTAR 0..N

CAPP_OPR-LARNT = CSLA-LSTAR

CSLA
MANDT [CLNT (3)]
KOKRS [CHAR (4)]
LSTAR [CHAR (6)]
DATBI [DATS (8)]

CAPP_OPR-INFNR = EINA-INFNR

EINA
MANDT [CLNT (3)]
INFNR [CHAR (10)]

CAPP_OPR-EBELP = EKPO-EBELP 0..N

EKPO
MANDT [CLNT (3)]
EBELN [CHAR (10)]
EBELP [NUMC (5)]

CAPP_OPR-LIFNR = LFA1-LIFNR 0..N

LFA1
MANDT [CLNT (3)]
LIFNR [CHAR (10)]

CAPP_OPR-ISTRU = MARA-MATNR

MARA
MANDT [CLNT (3)]
MATNR [CHAR (18)]

CAPP_OPR-PSPNR = PRPSS-PSPNR 0..N

CAPP_OPR-MANDT = T000-MANDT 0..N

PRPSS
MANDT [CLNT (3)]
PSPNR [NUMC (8)]

CAPP_OPR-BUKRS = T001-BUKRS 0..N

CAPP_OPR-WERKS = T001W-WERKS

T000
MANDT [CLNT (3)]

CAPP_OPR-TXTSP = T002-SPRAS 0..N

T001
MANDT [CLNT (3)]
BUKRS [CHAR (4)]

CAPP_OPR-ARBEH = T006-MSEHI 0..N

CAPP_OPR-BMEIH = T006-MSEHI

CAPP_OPR-DAUME = T006-MSEHI

T001W
MANDT [CLNT (3)]
WERKS [CHAR (4)]

CAPP_OPR-DAUNE = T006-MSEHI 0..N

CAPP_OPR-EHOFFB = T006-MSEHI

T002
SPRAS [LANG (1)]

CAPP_OPR-EHOFFE = T006-MSEHI

CAPP_OPR-MEINH = T006-MSEHI

CAPP_OPR-QRASTEREH = T006-MSEHI

CAPP_OPR-USE04 = T006-MSEHI 0..N

CAPP_OPR-USE05 = T006-MSEHI 0..N

CAPP_OPR-VGE01 = T006-MSEHI 0..N

CAPP_OPR-VGE02 = T006-MSEHI

CAPP_OPR-VGE03 = T006-MSEHI 0..N

CAPP_OPR-VGE04 = T006-MSEHI

CAPP_OPR-VGE05 = T006-MSEHI 0..N

CAPP_OPR-VGE06 = T006-MSEHI

CAPP_OPR-ZEIER = T006-MSEHI 0..N

CAPP_OPR-ZEILM = T006-MSEHI

CAPP_OPR-ZEILP = T006-MSEHI 0..N

CAPP_OPR-ZEIMB = T006-MSEHI

CAPP_OPR-ZEIMU = T006-MSEHI 0..N

CAPP_OPR-ZEITN = T006-MSEHI

CAPP_OPR-ZEIWN = T006-MSEHI 0..N

CAPP_OPR-ZEIWN = T006-MSEHI

T006
MANDT [CLNT (3)]
MSEHI [UNIT (3)]

CAPP_OPR-MATKL = T023-MATKL

T023
MANDT [CLNT (3)]
MATKL [CHAR (9)]

CAPP_OPR-EKGRP = T024-EKGRP 0..N

CAPP_OPR-EKORG = T024E-EKORG

T024
MANDT [CLNT (3)]
EKGRP [CHAR (3)]

CAPP_OPR-ANLZU = T357M-ANLZU

T024E
MANDT [CLNT (3)]
EKORG [CHAR (4)]

CAPP_OPR-LOGRP = T421-LOGRP 0..N

T357M
MANDT [CLNT (3)]
ANLZU [CHAR (1)]

CAPP_OPR-QUALF = T423-QUALF

T421
MANDT [CLNT (3)]
WERKS [CHAR (4)]
LOGRP [CHAR (3)]

CAPP_OPR-RFSCH = T425-RFSCH 0..N

CAPP_OPR-RFGRP = T426-RFGRP

T423
MANDT [CLNT (3)]
WERKS [CHAR (4)]
QUALF [CHAR (2)]

CAPP_OPR-RASCH = T428-RASCH 0..N

CAPP_OPR-ZERMA = T429-ZERMA

T425
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RFGRP [CHAR (10)]
RFSCH [CHAR (10)]

CAPP_OPR-STEUS = T430-STEUS 0..N

T426
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RFGRP [CHAR (10)]

CAPP_OPR-MLSTN = T433-MLSTN 0..N

T428
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RASCH [CHAR (2)]

CAPP_OPR-KTSCH = T435-VLSCH 0..N

T429
MANDT [CLNT (3)]
WERKS [CHAR (4)]
ZERMA [CHAR (5)]

CAPP_OPR-VERTL = T498-VERTL 0..N

T430
MANDT [CLNT (3)]
PLNAW [CHAR (1)]
STEUS [CHAR (4)]

CAPP_OPR-RSTRA = T499Q-RSTRA 0..N

T433
MANDT [CLNT (3)]
MLSTN [CHAR (5)]

CAPP_OPR-QLOTYPE = T778O-OTYPE 0..N

T435
MANDT [CLNT (3)]
VLSCH [CHAR (7)]

CAPP_OPR-KAPAR = TC26-KAPAR 0..N

T498
MANDT [CLNT (3)]
VERTL [CHAR (2)]

CAPP_OPR-QLKAPAR = TC26-KAPAR

T499Q
MANDT [CLNT (3)]
WERKS [CHAR (4)]
RSTRA [CHAR (2)]

CAPP_OPR-VERTN = TC29-VERTL 0..N

T778O
MANDT [CLNT (3)]
OTYPE [CHAR (2)]

CAPP_OPR-ZGR01 = TC31-ID 0..N

TC26
MANDT [CLNT (3)]
KAPAR [CHAR (3)]

CAPP_OPR-ZGR02 = TC31-ID 0..N

TC29
MANDT [CLNT (3)]
VERTL [CHAR (8)]

CAPP_OPR-ZGR03 = TC31-ID 0..N

CAPP_OPR-ZGR04 = TC31-ID 0..N

CAPP_OPR-ZGR05 = TC31-ID 0..N

CAPP_OPR-ZGR06 = TC31-ID 0..N

TC31
MANDT [CLNT (3)]
ID [CHAR (3)]

CAPP_OPR-PHSEQ = TC52-PHSEQ 0..N

TC52
MANDT [CLNT (3)]
WERKS [CHAR (4)]
PHSEQ [CHAR (2)]

CAPP_OPR-PLNTY = TCA01-PLNTY 0..N

TCA01
MANDT [CLNT (3)]
PLNTY [CHAR (1)]

CAPP_OPR-BZOFFB = TCA54-BZOFF 0..N

CAPP_OPR-BZOFFE = TCA54-BZOFF 0..N

TCA54
MANDT [CLNT (3)]
BZOFF [CHAR (2)]

CAPP_OPR-RUZUS = TCERS-RUZUS 0..N

TCERS
MANDT [CLNT (3)]
RUZUS [CHAR (4)]

CAPP_OPR-CKSELKZ = TCK08-SELKZ 0..N

TCK08
MANDT [CLNT (3)]
SELKZ [CHAR (1)]

CAPP_OPR-SLWID = TCN00-SLWID 0..N

TCN00
MANDT [CLNT (3)]
SLWID [CHAR (7)]

CAPP_OPR-NPRIO = TCN07-NPRIO 0..N

TCN07
MANDT [CLNT (3)]
NPRIO [CHAR (1)]

CAPP_OPR-RFPNT = TCNRFP-RFPNT 0..N

TCNRFP
MANDT [CLNT (3)]
RFPNT [CHAR (20)]

CAPP_OPR-USE06 = TCURC-WAERS 0..N

CAPP_OPR-USE07 = TCURC-WAERS 0..N

CAPP_OPR-WAERS = TCURC-WAERS 0..N

TCURC
MANDT [CLNT (3)]
WAERS [CUKY (5)]

CAPP_OPR-KALID = TFACD-IDENT 0..N

TFACD
IDENT [CHAR (2)]

CAPP_OPR-ANFKOKRS = TKA01-KOKRS 0..N

TKA01
MANDT [CLNT (3)]
KOKRS [CHAR (4)]

CAPP_OPR-PDEST = TSP03-PADEST 0..N

TSP03
PADEST [CHAR (4)]