SAP ABAP table CCGLS_ARESB {EHS: Reservation/Dependent Requirement - Old}

CCGLS_ARESB
- *MANDT* [CLNT (3)]
- *MATNR* [CHAR (18)]
- *WERKS* [CHAR (4)]
- *LGORT* [CHAR (4)]
- *CHARG* [CHAR (10)]
- *SOBKZ* [CHAR (1)]
- *MEINS* [UNIT (3)]
- *WAERS* [CUKY (5)]
- *ERFME* [UNIT (3)]
- *PLNUM* [CHAR (10)]
- *BNFPO* [NUMC (5)]
- *AUFNR* [CHAR (12)]
- *BAUGR* [CHAR (18)]
- *SERNR* [CHAR (8)]
- *KDAUF* [CHAR (10)]
- *BWART* [CHAR (3)]
- *GSBER* [CHAR (4)]
- *UMWRK* [CHAR (4)]
- *UMLGO* [CHAR (4)]
- *NOMAT* [CHAR (18)]
- *POSTP* [CHAR (1)]
- *ROMEI* [UNIT (3)]
- *RFORM* [CHAR (2)]
- *LTXSP* [LANG (1)]
- *SANKA* [CHAR (1)]
- *AENNR* [CHAR (12)]
- *VERTI* [CHAR (4)]
- *BEIKZ* [CHAR (1)]
- *ERSKZ* [CHAR (1)]
- *EBELN* [CHAR (10)]
- *EBELP* [NUMC (5)]
- *EBELE* [NUMC (4)]
- *KNTTP* [CHAR (1)]
- *OBJNR* [CHAR (22)]
- *FLGAT* [CHAR (1)]
- *EKGRP* [CHAR (3)]
- *ROKME* [UNIT (3)]
- *ZUMEI* [UNIT (3)]
- *PREEG* [CHAR (2)]
- *LGNUM* [CHAR (3)]
- *LGTYP* [CHAR (3)]
- *LGPLA* [CHAR (10)]
- *MATKL* [CHAR (9)]
- *LIFNR* [CHAR (10)]
- *FUNCT* [CHAR (3)]
- *INFNR* [CHAR (10)]
- *NLFMV* [UNIT (3)]
- *PRIO_URG* [NUMC (2)]
- *PRIO_REQ* [NUMC (3)]

CCGLS_ARESB-AENNR = AENR-AENNR (0..N) → **AENR** [MANDT (CLNT (3)), AENNR (CHAR (12))]

CCGLS_ARESB-AUFNR = AUFK-AUFNR (0..N) → **AUFK** [MANDT (CLNT (3)), AUFNR (CHAR (12))]

CCGLS_ARESB-BNFPO = EBAN-BNFPO (0..N) → **EBAN** [MANDT (CLNT (3)), BANFN (CHAR (10)), BNFPO (NUMC (5))]

CCGLS_ARESB-INFNR = EINA-INFNR (0..N) → **EINA** [MANDT (CLNT (3)), INFNR (CHAR (10))]

CCGLS_ARESB-EBELE = EKET-ETENR (0..N) → **EKET** [MANDT (CLNT (3)), EBELN (CHAR (10)), EBELP (NUMC (5)), ETENR (NUMC (4))]

CCGLS_ARESB-EBELN = EKKO-EBELN (0..N) → **EKKO** [MANDT (CLNT (3)), EBELN (CHAR (10))]

CCGLS_ARESB-EBELP = EKPO-EBELP (0..N) → **EKPO** [MANDT (CLNT (3)), EBELN (CHAR (10)), EBELP (NUMC (5))]

CCGLS_ARESB-LGPLA = LAGP-LGPLA (0..N) → **LAGP** [MANDT (CLNT (3)), LGNUM (CHAR (3)), LGTYP (CHAR (3)), LGPLA (CHAR (10))]

CCGLS_ARESB-LIFNR = LFA1-LIFNR (0..N) → **LFA1** [MANDT (CLNT (3)), LIFNR (CHAR (10))]

CCGLS_ARESB-BAUGR = MARA-MATNR (0..N) → **MARA** [MANDT (CLNT (3)), MATNR (CHAR (18))]

CCGLS_ARESB-MATNR = MARA-MATNR (0..N)

CCGLS_ARESB-NOMAT = MARA-MATNR (0..N)

CCGLS_ARESB-CHARG = MCHA-CHARG (0..N) → **MCHA** [MANDT (CLNT (3)), MATNR (CHAR (18)), WERKS (CHAR (4)), CHARG (CHAR (10))]

CCGLS_ARESB-OBJNR = ONR00-OBJNR (1) → **ONR00** [MANDT (CLNT (3)), OBJNR (CHAR (22))]

CCGLS_ARESB-PLNUM = PLAF-PLNUM (0..N) → **PLAF** [MANDT (CLNT (3)), PLNUM (CHAR (10))]

CCGLS_ARESB-PRIO_REQ = PREQ-PRIO_REQ (0..N) → **PREQ** [MANDT (CLNT (3)), PRIO_REQ (NUMC (3))]

CCGLS_ARESB-PRIO_URG = PURG-PRIO_URG (0..N) → **PURG** [MANDT (CLNT (3)), PRIO_URG (NUMC (2))]

CCGLS_ARESB-SERNR = SNUM-SERNR (0..N) → **SNUM** [MANDT (CLNT (3)), SERNR (CHAR (8))]

CCGLS_ARESB-MANDT = T000-MANDT (0..N) → **T000** [MANDT (CLNT (3))]

CCGLS_ARESB-LGORT = T001L-LGORT (0..N) → **T001L** [MANDT (CLNT (3)), WERKS (CHAR (4)), LGORT (CHAR (4))]

CCGLS_ARESB-UMLGO = T001L-LGORT (0..N)

CCGLS_ARESB-UMWRK = T001W-WERKS (0..N) → **T001W** [MANDT (CLNT (3)), WERKS (CHAR (4))]

CCGLS_ARESB-WERKS = T001W-WERKS (0..N)

CCGLS_ARESB-LTXSP = T002-SPRAS (1) → **T002** [SPRAS (LANG (1))]

CCGLS_ARESB-ERFME = T006-MSEHI (0..N) → **T006** [MANDT (CLNT (3)), MSEHI (UNIT (3))]

CCGLS_ARESB-MEINS = T006-MSEHI (0..N)

CCGLS_ARESB-NLFMV = T006-MSEHI (0..N)

CCGLS_ARESB-ROKME = T006-MSEHI (0..N)

CCGLS_ARESB-ROMEI = T006-MSEHI (0..N)

CCGLS_ARESB-ZUMEI = T006-MSEHI (0..N)

CCGLS_ARESB-MATKL = T023-MATKL (1..N) → **T023** [MANDT (CLNT (3)), MATKL (CHAR (9))]

CCGLS_ARESB-EKGRP = T024-EKGRP (0..N) → **T024** [MANDT (CLNT (3)), EKGRP (CHAR (3))]

CCGLS_ARESB-SOBKZ = T148-SOBKZ (0..N) → **T148** [MANDT (CLNT (3)), SOBKZ (CHAR (1))]

CCGLS_ARESB-BWART = T156-BWART (0..N) → **T156** [MANDT (CLNT (3)), BWART (CHAR (3))]

CCGLS_ARESB-KNTTP = T163K-KNTTP (0..N) → **T163K** [MANDT (CLNT (3)), KNTTP (CHAR (1))]

CCGLS_ARESB-LGNUM = T300-LGNUM (0..N) → **T300** [MANDT (CLNT (3)), LGNUM (CHAR (3))]

CCGLS_ARESB-LGTYP = T301-LGTYP (0..N) → **T301** [MANDT (CLNT (3)), LGNUM (CHAR (3)), LGTYP (CHAR (3))]

CCGLS_ARESB-ERSKZ = T413-ERSKZ (0..N) → **T413** [MANDT (CLNT (3)), ERSKZ (CHAR (1))]

CCGLS_ARESB-BEIKZ = T417-BEIKZ (0..N) → **T417** [MANDT (CLNT (3)), BEIKZ (CHAR (1))]

CCGLS_ARESB-POSTP = T418-POSTP (0..N) → **T418** [MANDT (CLNT (3)), POSTP (CHAR (1))]

CCGLS_ARESB-RFORM = T418F-RFORM (0..N) → **T418F** [MANDT (CLNT (3)), RFORM (CHAR (2))]

CCGLS_ARESB-VERTI = T437V-VERTL (0..N) → **T437V** [MANDT (CLNT (3)), WERKS (CHAR (4)), VERTL (CHAR (4))]

CCGLS_ARESB-PRREG = T441R-PRREG (0..N) → **T441R** [MANDT (CLNT (3)), PRREG (CHAR (2))]

CCGLS_ARESB-FUNCT = TC29V-FUNCT (1) → **TC29V** [MANDT (CLNT (3)), FUNCT (CHAR (3))]

CCGLS_ARESB-FLGAT = TCA07-FLGAT (0..N) → **TCA07** [FLGAT (CHAR (1))]

CCGLS_ARESB-SANKA = TCK08-SELKZ (0..N) → **TCK08** [MANDT (CLNT (3)), SELKZ (CHAR (1))]

CCGLS_ARESB-WAERS = TCURC-WAERS (0..N) → **TCURC** [MANDT (CLNT (3)), WAERS (CUKY (5))]

CCGLS_ARESB-GSBER = TGSB-GSBER (0..N) → **TGSB** [MANDT (CLNT (3)), GSBER (CHAR (4))]

CCGLS_ARESB-KDAUF = VBUK-VBELN (0..N) → **VBUK** [MANDT (CLNT (3)), VBELN (CHAR (10))]